Cisco Packet Tracer-based Assessment Environment Check

Requirements

- Java enabled web browser (minimal JRE version 1.7.0)
- Packet Tracer software installed (minimal PT version 6.0.1)
- Internet

Successful check

Browse to http://skills.netacad.net/check/check.html

It will install the first time some extra plugins from netacad.
Finally you should have next output.

Failed check due to PT

When the output is like this, your 'system environment variable' isn't correct.

Cisco Packet Tracer-based Assessment Environment Check

This page contains a Java applet that will verify that your computer is ready to run Packet Tracer-based assessment items.

The entries below will display the information determined by the applet. If there are any „ERROR" messages, your computer needs some adjustment before you attempt a Packet Tracer-based assessment items.

After the check has completed, close this window to return to Netspace.

Browser Name -- N/A

Large File Download Capability -- Unknown

JRE Version -- 1.7.0_67

Packet Tracer Skills Assessment Player Patch Files Available -- Yes

Packet Tracer Skills Assessment Player Program File Available -- Yes

Operating System Name -- Windows 8

Packet Tracer Deployment Directory -- Not found
> **ERROR** -- Your current environment variables don't allow us to find a candidate Packet Tracer installation directory. You may identify the proper Packet Tracer installation directory by setting the value of one of these operating system environment variables: PT6HOME,PT5HOME,PT_LAUNCH_DIR,PTDIR; or by adding Packet Tracer's "bin" subdirectory to your PATH environment variable.

Packet Tracer IPC Ports Available -- Unknown

Packet Tracer Version -- Unknown

Signed Applet Access Granted -- Yes

The check has failed. Your computer requires additional configuration to run Cisco Packet Tracer-based assessments.

Go to System

Select Advanced system settings

Select Environment Variables...

Select New…

Variable name: **PT6HOME**
Variable value: **C:\Program Files (x86)\Cisco Packet Tracer 6.1.1sv** (root directory PT)

Click OK
Click OK
Click OK

Restart web browser.

Browse to http://skills.netacad.net/check/check.html