



BBMe Ping

A from-scratch, free add-on for BBM Enterprise: triggers a fully configurable tone/repeat pattern for priority messages that stays audible even in silent mode – depending on the sender and the phone's current mode. This guide shows what the app does and how to set it up.

Version 0.12 · GNU GPLv3 (or later) · no BBM code, no bundled BBM sounds

Source code & APK: github.com/8818freak/BBMePing

All screenshots are from real use; the app is also available in English (follows the device language), but the screenshots below were taken with the device set to German.

Contents


1. [What is BBMe Ping?](#)
2. [Setup](#)
3. [Setting the default pattern](#)
4. [Choosing a sound](#)
5. [Per-contact patterns](#)
6. [Backup](#)
7. [About BBMe Ping](#)

1 What is BBMe Ping?

BlackBerry's messenger successor BBM Enterprise has messages with elevated priority (formerly known as "PING"). On a silenced phone that's easy to miss – BBM Enterprise does vibrate, but plays no sound of its own against the silence setting. **BBMe Ping** closes exactly that gap: it watches for priority notifications from BBM Enterprise and triggers a freely composed tone/repeat pattern for them, deliberately routed through the alarm volume channel – the same one alarm-clock apps use to stay audible even in "Silent" mode.

Free · open source (GPLv3) · no BBM code, no bundled BBM sounds · no tracking, no ads · German/English (follows device language) · Android 10 or newer.

BBMe Ping contains no BlackBerry/BBM graphics, sounds or code – it talks only to open, documented Android interfaces (NotificationListenerService, to detect priority notifications and read the sound BBM itself configured for them, and ContactsContract for per-contact patterns).



Main screen

2 Setup


Grant notification access

Without this, BBMe Ping cannot detect BBM messages at all – the app shows this hint at the top for as long as access is missing. Tapping "Grant access" opens the system's notification-access screen; find BBMe Ping in the list there and turn it on.

This is the very same system screen used to grant notification access to any other app (e.g. a call-blocker) – not a special BBMe Ping dialog, just plain Android.

Optional but recommended: grant contacts access the first time you set up a per-contact pattern (see [section 5](#)) – without it, every sender falls back to the default pattern.

Important when a permission changes: if a permission changes – e.g. an update adds a new one or widens an existing one – you must **revoke the already-granted permission in Android settings and grant it again**. Otherwise it stays ineffective even though it shows as “granted”.



Permissions explained

3 Setting the default pattern

Tone sequence

“Tones per sequence” sets how many tones play right after each other (with “gap between tones” in between) before a longer pause follows.

Repeats & gaps


“Repeats” counts the additional repetitions of the whole sequence (0 = play once only). “Gap between sequences” is the longer pause between two such repeats.

Volume

Starting and (optionally) maximum volume, ramping linearly across all repeats – e.g. start quiet and get louder by the last repeat.

Phone mode

The pattern only applies in the checked modes (Normal/Vibrate/Silent). Leaving “Silent” unchecked would remove the whole point of the app exactly where it matters most – worth double-checking which modes are active.



Pattern editor

4 Choosing a sound

Automatic (default)

Without a custom choice, BBMe Ping reads the sound BBM Enterprise itself configured for its notification channel on every real priority message – no sound file is ever copied or bundled, it's only read at runtime.

Choose a sound from BBMe...

Lists the sounds of the actually installed BBM Enterprise app directly (e.g. "Priority (PING)") and resolves them against BBM's own resources – again nothing is copied, only a reference is stored. Adapts automatically if BBM ever changes its sounds.

Choose custom file...

Pick any sound file from the device (e.g. an old BBM tone you saved yourself).

Test

Plays the configured sound (or the one last observed on a real message) once, with the full pattern.

5 Per-contact patterns


"+ Add contact" lets you set a pattern for one sender that replaces the default pattern for them (only while it's active for the current phone mode – otherwise the default pattern applies again). Matching is done against the exact display name from the address book, so the wrong person is never matched by mistake. Remove a contact again any time via the X next to its entry.

6 Backup

Under “About BBMe Ping” → “Backup”, the default pattern and all per-contact patterns can be exported to a plain text file, or restored from one (handy before a reinstall, or to move patterns to another device). Automatically-detected and “chosen from BBMe” sounds carry over fine; a file picked via “Choose custom file...” only stays valid on the same device.

7 About BBMe Ping

Shows the installed version, the full license text (GPLv3), and a collapsible changelog at any time – right inside the app, no internet needed. A diagnostic log records any errors/crashes (helps with troubleshooting without a cable).



About BBMe Ping (version, licence, backup)