

IBM Education Assistance for z/OS V2R1

Item: SMS ACS Read-only Variable for EAV

Component: DFSMSdfp SMS





Agenda

- Trademarks
- Presentation Objectives
- Overview
- Usage & Invocation
- Interactions & Dependencies
- Migration & Coexistence Considerations
- Presentation Summary
- Appendix



Trademarks

See url http://www.ibm.com/legal/copytrade.shtml for a list of trademarks.



Presentation Objectives

- Understand why customers requested a new ACS Read-only Variable for EAV
- Learn the new ACS Read-only Variable for EAV and its expected values



Overview

- Problem Statement / Need Addressed
 - -Currently, the EATTR keyword can be specified on
 - JCL
 - Dynamic allocation
 - AMS DEFINE
 - DATACLAS
 - -However, it's NOT available to the installation's ACS routines
- Solution
 - -Provide a new ACS Read-only Variable for EAV &EATTR
- Benefit / Value
 - ACS routines can be more intelligent to select proper SMS constructs for EAV, so a data set can be allocated to an EAV storage group



Overview

- ACS Read-only Variable for EAV
 - -Name: &EATTR
 - Description: contains the EATTR value. EATTR means extended attributes, currently only for EAV
 - –Expected Values:
 - OPT : extended attributes are optional
 - NO : no extended attributes
 - Blank: not specified (This is a default value)
- &EATTR Value Availability to ACS routines
 - DATACLAS ACS routine if specified on JCL, AMS DEFINE, or Dynamic Allocate
 - -STORCLAS ACS routine if specified
 - –MGMTCLAS ACS routine if specified
 - -STORGRP ACS routine if specified



Usage & Invocation

■ The ACS routine programmer can test &EATTR in the ACS routines.



Interactions & Dependencies

- Software Dependencies
 - -None
- Hardware Dependencies
 - -None
- Exploiters
 - –ACS routine programmers
 - -Storage management admins



Migration & Coexistence Considerations

- &EATTR is only available on z/OS V2R1 systems
- IBM recommends lower releases should not reference &EATTR
 - -If the ACS routines are written and activated on V2R1, the programmer needs to add a logic to jump around all the references to &EATTR
 - Otherwise, in lower releases, ACS processing will fail with the existing return code 20 and reason code 2035, which means invalid ACS Readonly variable



Presentation Summary

- A new ACS Read-only Variable for EAV &EATTR
- &EATTR Value Availability to ACS routines



Appendix

- Publication references:
 - -z/OS DFSMSdfp Storage Administration