Course Title: Graphic Designing

Course Code: CIT - 344

LECTURE 03:

Adobe Photoshop



Topics covered

- 3.1 Use Magic Wand Tool
- 3.2 Use Polygonal Lasso Tool
- 3.3 Use Pen Tool
- 3.4 Change Colors with Edit in Quick Mask Mode
- 3.5 Shining Face
- 3.6 Brightness Face
- 3.7 Photo Retouching

Prepared by: **Engr. Miss. Ayesha Zulfiqar**

3.1 Use Magic Wand Tool



Definition

The Magic Wand Tool is a selection tool in Adobe Photoshop used to select areas of similar colors in an image.

Purpose

It is commonly used to select plain backgrounds, solid-colored areas, and objects with similar colors.

Steps to Use the Magic Wand Tool

1. Open Adobe Photoshop.
2. Click File → Open and select an image.
3. Select the Magic Wand Tool (W) from the toolbar. It may be grouped with other selection tools.
4. Click on the color or area you want to select.
5. Adjust the Tolerance value in the Options Bar if needed.
6. Hold `Shift` and click other areas to add them to the selection.
7. Hold `Alt` and click to subtract areas from the selection.
8. Use the selection to change color, delete pixels, or apply an adjustment.

Important Options

- Tolerance: Controls how much color variation is included in the selection.
- Contiguous: When enabled, selects similar-colored pixels connected to the clicked area.
- Anti-alias: Helps smooth the edges of a selection.
- Sample All Layers: Allows sampling visible content across layers when supported by the current tool settings.

Example

To remove a plain white background from a product photograph, click the white area with the Magic Wand Tool, check the selection, and remove or mask the selected background.

Remember: The Magic Wand Tool selects areas based on color similarity.

3.2 Use Polygonal Lasso Tool



Definition

The Polygonal Lasso Tool is a selection tool used to select objects by creating straight lines around their edges.

Purpose

It is useful for selecting objects with straight or angular boundaries, such as buildings, boxes, books, and geometric shapes.

Steps to Use the Polygonal Lasso Tool

1. Open an image in Photoshop.
2. Select the Polygonal Lasso Tool (L) from the toolbar. It may be grouped with other Lasso tools.
3. Click on the starting point of the object.
4. Click along the object's edges to create straight selection segments.
5. Continue clicking around the object.
6. Return to the starting point and click to close the selection.
7. Check the selected area.
8. Copy the selection to a new layer using `Ctrl + J`, or apply a suitable adjustment.

Example

To select a book from a photograph, click around the book's corners and edges with the Polygonal Lasso Tool.

Important Points

- It creates selections using straight lines.
- It is suitable for angular objects.
- Each click creates a new point.
- The selection must be closed to complete the process.
- For curved objects, other selection tools may be more suitable.

Remember: The Polygonal Lasso Tool is best for objects with straight edges.

3.3 Use Pen Tool



Definition

The Pen Tool is a tool in Adobe Photoshop used to create precise paths using anchor points and direction handles.

Purpose

The Pen Tool is commonly used for accurate object outlines, smooth curves, custom shapes, and selections.

Steps to Use the Pen Tool

1. Open an image in Photoshop.
2. Select the Pen Tool (P) from the toolbar.
3. In the Options Bar, choose Path mode when creating a path for a selection.
4. Click on the edge of the object to create the first anchor point.
5. Click again at another point to create a straight path segment.
6. Click and drag to create curved segments.
7. Continue placing anchor points around the object.
8. Close the path by clicking the starting anchor point.
9. Open the Paths panel and select the completed path.
10. Choose Make Selection to convert the path into a selection.

Example

A student can use the Pen Tool to trace a shoe accurately and separate it from the background.

Important Terms


- Anchor Point: A point that controls the position of a path.
- Path: A line or outline created using anchor points.
- Direction Handles: Controls that help shape curved path segments.
- Selection: An area chosen for editing.

Advantages of the Pen Tool

- Creates precise outlines.
- Supports smooth curves and straight lines.
- Helps select objects with complex edges.
- Allows paths to be edited before converting them into selections.

Remember: The Pen Tool creates paths, which can then be converted into selections.

3.4 Change Colors with Edit in Quick Mask Mode



Definition

Quick Mask Mode is a Photoshop feature used to create and refine selections by painting over areas of an image.

Purpose

It helps select specific parts of an image accurately so that colors or other adjustments can be applied only to the desired area.

Steps to Change Colors Using Quick Mask Mode

1. Open an image in Photoshop.
2. Select the Brush Tool (B).
3. Press Q to enter Quick Mask Mode.
4. Paint over the area you want to isolate. The mask overlay typically appears red.
5. Use black and white brush colors to refine the mask according to the current Quick Mask settings.
6. Press Q again to exit Quick Mask Mode and convert the mask into a selection.
7. Go to Layer → New Adjustment Layer → Hue/Saturation.
8. Move the Hue, Saturation, and Lightness sliders to change the selected area's appearance.
9. Adjust the mask if needed, and save the file.

Example

To change the color of a shirt in a photograph, paint over the shirt in Quick Mask Mode, convert the mask into a selection, and adjust its color using Hue/Saturation.

Important Points

- Press ⍳ to enter or exit Quick Mask Mode.
- The red overlay represents masked areas, not necessarily the selected areas.
- Use the Brush Tool to refine the mask.
- An adjustment layer helps preserve the original image pixels.

Remember: Quick Mask Mode helps create and refine selections for targeted editing.

3.5 Shining Face



Definition

Shining Face is a photo-editing technique used to create a soft, healthy glow on a person's face by enhancing highlights and improving the overall appearance of the skin.

Purpose

This technique is used in portrait photography, beauty photography, and professional photo editing to make the face appear brighter and more radiant while maintaining a natural look.

Steps to Create a Shining Face Effect

1. Open a portrait photograph in Adobe Photoshop.
2. Duplicate the image layer by pressing `Ctrl + J`.
3. Go to Filter → Camera Raw Filter, if available in your version.
4. Slightly increase the Highlights and Exposure to brighten the image.
5. Adjust Texture and Clarity carefully to avoid making skin look unnatural.
6. Click OK to apply the changes.
7. Add a layer mask to the edited layer.
8. Use a soft black brush on the mask to hide the effect from areas that should not be brightened.
9. Reduce the layer opacity if the effect is too strong.
10. Save the edited image.

Important Points

- Apply the glow subtly.
- Avoid overexposing the forehead, nose, and cheeks.
- Keep natural skin texture visible.
- Use a layer mask to control where the effect appears.

Example: Enhancing soft highlights on a person's cheeks and forehead for a portrait photograph.

Remember: The shining face effect enhances highlights to create a soft, radiant appearance.

3.6 Brightness Face



Definition

Face Brightness is a photo-editing technique used to increase the brightness of a person's face so that facial features are more clearly visible.

Purpose

It is useful when a face appears dark because of poor lighting, shadows, or incorrect exposure.

Steps to Brighten a Face

1. Open a portrait photograph in Photoshop.
2. Duplicate the image layer using `Ctrl + J`.
3. Select the Lasso Tool (L) or another suitable selection tool.
4. Carefully select the face area.
5. Refine the selection edges if necessary.
6. Go to Layer → New Adjustment Layer → Brightness/Contrast.
7. Increase Brightness gradually until the face looks properly exposed.
8. Adjust Contrast if required.
9. Check the result against the rest of the photograph.
10. Save the file in PSD format to preserve the adjustment layer.

Important Points

- Brighten only the areas that need correction.
- Avoid making the face look unnaturally white.
- Maintain the natural skin tone.
- Use a soft layer mask to blend the adjustment with surrounding areas.

Difference between Shining Face and Brightness Face

Shining Face	Brightness Face
Creates a soft glow and highlights.	Corrects a face that looks too dark.
Focuses on radiant appearance.	Focuses on exposure and visibility.
Often enhances selected highlights.	Increases brightness in the selected face area.
Used mainly for a glowing portrait effect.	Used mainly to correct lighting problems.

Remember: Brightness Face corrects darkness, while Shining Face enhances the glow.

3.7 Photo Retouching



Definition

Photo retouching is the process of correcting and improving a photograph by removing unwanted marks, correcting colors, improving lighting, and fixing minor imperfections.

Purpose

Photo retouching is used to improve image quality and create a clean, professional appearance while preserving important details.

Common Photo Retouching Techniques

1. Blemish Removal: Removes small spots and temporary marks.
2. Skin Retouching: Improves uneven areas while retaining natural texture.
3. Color Correction: Adjusts colors to make the photograph look balanced.
4. Brightness and Contrast: Improves visibility and tonal balance.
5. Red-Eye Correction: Corrects the red appearance of eyes caused by flash photography.
6. Sharpening: Enhances the appearance of details.
7. Background Cleanup: Removes unwanted objects or distractions.

Steps to Retouch a Photograph

1. Open the photograph in Adobe Photoshop.
2. Duplicate the original layer using `Ctrl + J`.
3. Select the Spot Healing Brush Tool (J).
4. Adjust the brush size to match the spot you want to correct.
5. Click or carefully paint over small blemishes.
6. Use the Healing Brush Tool for areas that need more control over the sampled texture.
7. Use Brightness/Contrast or Curves adjustment layers to correct lighting.
8. Correct color balance if needed.
9. Zoom in to check details and zoom out to review the complete image.
10. Save the working file in PSD format and export a final copy in JPEG or PNG as required.

Important Points

- Always preserve an original copy.
- Avoid excessive skin smoothing.
- Maintain natural skin texture.
- Use non-destructive adjustments when possible.
- Check the photograph at both close-up and normal viewing sizes.

Example: Retouching a portrait by removing a temporary blemish, correcting uneven lighting, and improving the overall color balance.

Remember: Photo retouching improves the quality and appearance of a photograph by correcting imperfections.

Important shortcut keys for this lecture

Shortcut	Function
W	Select the Magic Wand Tool or another tool in its group
L	Select the Lasso Tool or a tool in its group
P	Select the Pen Tool
Q	Enter or exit Quick Mask Mode
B	Select the Brush Tool
J	Select the Healing Brush tool group
Ctrl + J	Duplicate a layer or copy selected pixels to a new layer
Ctrl + S	Save the document

Short questions

1. What is the Magic Wand Tool?
2. What is the purpose of the Tolerance option?
3. Define the Polygonal Lasso Tool.
4. What is the Pen Tool used for?
5. What is an anchor point?
6. Define Quick Mask Mode.
7. Which shortcut is used to enter Quick Mask Mode?
8. What is the Shining Face effect?
9. Why is Brightness Face used?
10. Define photo retouching.
11. Write any four photo retouching techniques.
12. Why should the original image be preserved during retouching?

Long questions

1. Explain the Magic Wand Tool with its steps and options.
2. Describe how to select an object using the Polygonal Lasso Tool.
3. Explain how the Pen Tool creates precise selections.
4. Describe the procedure for changing colors using Quick Mask Mode.
5. Explain the steps for creating a Shining Face effect.
6. Describe how to brighten a face in Photoshop.
7. Define photo retouching and explain its common techniques.