Time Scaler

v1.2.0


Time Scaler is a simple editor tool that can help debug things in slow motion, speed up, or pause.

Core features:

- Easily change the time scale for testing purposes using the slider.
- Set up to 10 time scale presets for all possible use cases.
- Ability to store different presets in the lists in scriptable objects.
- Reset the time scale on game start or stop.
- Keyboard shortcuts for applying presets without the need to use your mouse.


[0] Installation

After you download and import the package from the Asset Store, a new menu item will appear under the ‘Window’ tab. Click on it to open the window.



[1] Usage

This is the main tab of the tool. Here you can see the current time scale together with options to manipulate it.




Current Time Scale - current time scale of the project that is set in '**Project Settings/Time**'.

Slider Range - minimum and maximum values that can be set using the slider below.
Update Time Scale - slider to easily change the current time scale without creating a preset. You have to press the ‘Apply’ button to make it work.

Presets - by default, there are only 2 presets: ‘Default’ with the time scale 1 and ‘Paused’ with the time scale 0. You can add up to 10 presets that will be saved into Editor Preferences. When you finish, you can save your presets list into a scriptable file so it can be accessed by any of your team members when you add it to the repository. Setup below can be set by going to the ‘Presets List’ tab and choosing the ‘Documentation’ presets list.




Export Mode - you can choose to save the current preset list into a new file or overwrite the existing ones.
Presets to override - presets list that will be overwritten.




[2] Presets List

In this tab you can preview and apply all presets lists inside of your Unity Project. Presets are stored in the scriptables object so that you can have many different scenarios with different time scales. Also, they provide a way to be shared among team members (by adding them to the version control system or sending scriptable object files). By default, there are three possible preset lists.



[3] Settings

In this tab, you can adjust all available tools' settings. It also contains some helper buttons to reset the settings or presets to their default state.



Print usage logs - print a log to the console every time there is a time scale change caused by this tool.
Reset on game start - reset the time scale to the default value on game start.
Reset on game stop - reset the time scale to the default value on game stop.
Default Time Scale - default time scale value. Used when reset on game start/stop is enabled.

Slider range - minimum and maximum values that can be set using the time scale slider.
Line height - option to increase or decrease preset line height - bigger can be easier to click for some users.


Reset settings to defaults - reset all settings to their default values.
Resets presets to defaults - delete all presets from the editor preferences leaving only default and paused state.

Open the Project Settings on ‘Time’ tab - shortcut to open the project’s settings where you can manually override time scale and other values.

Enable / Disable shortcuts - button to toggle shortcuts (script will be changed, so recompile is necessary).

[4] Shortcuts

Each preset can be quickly applied using specified shortcuts. By default, they are all disabled to not conflict with some basic tools like ProBuilder or Version Control, but you can enable them in the ‘Settings’ tab. Default bindings can be found in the ‘Edit/Shortcuts’ window under the 'FCD-Time Scaler’ category.



[5] Review and Feedback

If you enjoyed using this tool please consider leaving a review on the **Unity Asset store** !
Thank you very much for any feedback.

Need some help or have an idea how to make this tool even better? Don't hesitate to write me an email at **contact@fewclicksdev.com**.