


Q: HOW TO INSTALL THE WINDOW USING VM WARE IN VIRTUAL MACHINE?

ANSWER:

STEP – 1:GO TO THE VIRTUAL MACHINE,




AND CLICK ON VM WARE APPLICATION.




STEP – 2: BY DEFAULT IT GO TO THE HOME PAGE, IN THAT CLICK ON CREATE A NEW PROJECT.

WIPRO ASSIGNMENT - 4




IT DISPLAYS A POP UP AS WELCOME TO THE NEW VIRTUAL MACHINE WIZARD,



CLICK ON NEXT,

STEP – 3: AGAIN IT DISPLAYS ANOTHER NOTIFICATION,


WIPRO ASSIGNMENT - 4



CLICK ON NEXT,

BY DEFAULT IT AUTOMATICALLY DISPLAYS AS I WILL INSTALL THE OPERATING SYSTEM LATER


STEP – 4: THE VIRTUAL MACHINE WILL BE CREATED WITH A BLANK HARD DISK.



CLICK ON NEXT,


IT AGAIN DISPLAYS ANOTHER NOTIFICATION FOR FURTHER STEP AS SHOWN BELOW:

WIPRO ASSIGNMENT - 4




BY DEFAULT IT SELECTS THE OPTION AS LINUX, WE NEED TO CHANGE THE OPTION AS MICROSOFT WINDOWS AND CLICK ON NEXT.

STEP – 5:CREATE A NEW FOLDER IN LOCAL DISK(C) AND GIVE THE FILE NAME AS Win10 -2.




NOW CLICK THE BROWSE OPTION AND SELECT THE PATH THAT WHICH WE CREATED.

WIPRO ASSIGNMENT - 4




IT DISPLAYS AS SHOWN ABOVE,

CLICK ON NEXT.



SELECT ON UEFI AND CLICK NEXT


WIPRO ASSIGNMENT - 4



STEP – 6:IT DISPLAYS THE PROCESSOR CONFIGURATION ,SELECT THE NUMBER AS WE REQUIRED.


NOW, CLICK NEXT.

IT DISPLAYS MEMORY FOR THE VIRTUAL MACHINE AS SHOWN BELOW AND CLICK NEXT.




STEP – 7:SELECT THE NETWORK TYPE AS USE NETWORK ADDRESS TRANSLATION(NAT)

WIPRO ASSIGNMENT - 4




SELECT THE I/O CONTROLLER TYPE AS LSI




NOW SELECT DISK TYPE AS NVMe

WIPRO ASSIGNMENT - 4




STEP – 8:NOW WE NEED TO SELECT A DISK → SELECT THE CREATE A NEW VIRTUAL DISK AND CLICK ON NEXT.




SELECT SPECIFIC DISK CAPACITY AS DEFAULT

WIPRO ASSIGNMENT - 4




AND CLICK ON NEXT

STEP – 9:NOW WE NEED TO SELECT THE DISK FILE BY USING THE BROWSE OPTION,




CLICK ON NEXT

WIPRO ASSIGNMENT - 4




STEP – 10:SELECT THE FINISH OPTION ON THE SCREEN.



IT DISPLAYS THE WIN 10-2 AS CREATED BUT WE NEED TO POWER IT ON BY DOUBLE


STEP – 11:CLICKING ON >POWER ON THE VIRTUAL MACHINE.

WIPRO ASSIGNMENT - 4




IT LOADS AND RUNS .

NOW WE NEED TO PRESS ANY KEY AND CLICK ON THE MIDDLE OF THE SCREEN.IF WE MISSED IT THEN IT DISPLAYS AS TIME OUT.




NO PROBLEM AGAIN WE CAN USE THE BUTTON WHICH REWORK AGAIN,



STEP – 12:TRY AGAIN WITH THE ABOVE STEP,


NEXT IT SHOWS THE WINDOW SYMBOL IF YOU WORK PROPERLY OTHERWISE IT WILL SHOW AS TIME OUT.




NOW IT TAKES SOME TIME TO LOAD THE PAGE.

AFTER THAT IT DISPLAYS AS SHOWN BELOW.


WIPRO ASSIGNMENT - 4




STEP -13:SELECT THE DEFAULT ITEMS AND CLICK ON NEXT,



WIPRO ASSIGNMENT - 4




STEP – 14:NOW SELECT THE INSTALL NOW OPTION AND CLICK ON IT.




NOW LIGHTLY SCROLL DOWN THE SCREEN AND SELECT I DON'T HAVE A PRODUCT KEY.


WIPRO ASSIGNMENT - 4




STEP – 15:NOW SELECT THE OPTION AS WINDOWS 10 PRO AND CLICK ON IT.



WIPRO ASSIGNMENT - 4




NOW ACCEPT THE LICENSE TERMS AND




CLICK ON NEXT.

WIPRO ASSIGNMENT - 4




STEP -16:SELECT THE 2ND OPTION CUSTOM AND CLICK ON IT.




CLICK ON NEXT,

WIPRO ASSIGNMENT - 4




NOW IT TAKES SEVERAL MINUTES TO GET INSTALL.




STEP -17:ONE BY ONE IT DOWNLOADS ALL THE REQUIRED TOOLS.

NOW IT SHOWS,

WIPRO ASSIGNMENT - 4




CLICK THE RIGHT BUTTON ON THE WIN10-2, GO TO THE SETTINGS.



NOW SELECT THE NETWORK ADAPTER OPTION .


WIPRO ASSIGNMENT - 4




STEP -18:NOW UNCHECK THE CONNECTED OPTION AND CLICK ON OK.

SELECT THE DEFAULT OPTION THAT IS UNITED STATES.


SCROLL DOWN AND CLICK ON NEXT BUTTON.



WIPRO ASSIGNMENT - 4




SELECT THE US OPTION → CLICK YES.




SELECT SKIP OPTION.

WIPRO ASSIGNMENT - 4




NOW SELECT THE I DON'T HAVE INTERNET OPTION,




STEP – 19:SELECT CONNECTED WITH LIMITED SETUP BUTTON AND NEXT IT DISPLAYS BY ASKING NAME OF THE WINDOW,

WE CAN GIVE AS WE WANT.

WIPRO ASSIGNMENT - 4





I HAVE GIVEN IT AS Win10-2




NOW IT ASKS FOR SECURITY QUESTIONS,

WIPRO ASSIGNMENT - 4




GIVE ALL 3 QUESTIONS AND GIVE THE ANSWERS.

WIPRO ASSIGNMENT - 4




NOW UNSELECT ALL THE YES BUTTONS AND CLICK ON NEXT,




NOW ACCEPT IT.

WIPRO ASSIGNMENT - 4




STEP – 20: GIVE THE NOT NOW OPTION


NOW IT LOADS;



WIPRO ASSIGNMENT - 4



SUCCESSFULLY WINDOWS ARE DOWNLOADED.



HENCE, ITS COMPLETED.

WIPRO ASSIGNMENT - 4