AWS S3 Boto3 Client Functions

Bucket Operations

- create bucket Creates a new S3 bucket.
- delete bucket Deletes an existing bucket.
- list_buckets Lists all S3 buckets owned by the AWS account.
- head_bucket Retrieves metadata about a bucket without returning the object itself.

Object Operations

- put_object Uploads an object to a bucket.
- get_object Downloads an object from a bucket.
- delete_object Deletes an object from a bucket.
- delete_objects Deletes multiple objects in a single request.
- copy_object Copies an object from one bucket to another.
- list_objects_v2 Lists objects in a bucket (newer version).
- list_objects Lists objects in a bucket (older version).
- head_object Retrieves metadata about an object without returning the object itself.

Multipart Upload Operations

- create_multipart_upload Initiates a multipart upload.
- upload_part Uploads a part in a multipart upload.
- complete_multipart_upload Completes a multipart upload.
- abort_multipart_upload Aborts a multipart upload.
- list_multipart_uploads Lists ongoing multipart uploads.
- list_parts Lists the parts uploaded for a specific multipart upload.

Presigned URLs

- generate_presigned_url Generates a temporary URL for accessing an object.
- generate_presigned_post Generates a temporary URL for uploading an object.

Bucket Policy & ACLs

- get_bucket_policy Retrieves the bucket's policy.
- put_bucket_policy Sets the bucket policy.
- delete_bucket_policy Deletes the bucket policy.
- get bucket acl Retrieves the buckets Access Control List (ACL).
- put_bucket_acl Updates the bucket ACL.

- get_object_acl Retrieves the ACL of an object.
- put_object_acl Updates the ACL of an object.

CORS Configuration

- get_bucket_cors Retrieves the CORS configuration for a bucket.
- put_bucket_cors Sets the CORS configuration for a bucket.
- delete_bucket_cors Deletes the CORS configuration for a bucket.

Logging Configuration

- get_bucket_logging Retrieves the logging configuration of a bucket.
- put_bucket_logging Sets the logging configuration for a bucket.

Tagging

- get_bucket_tagging Retrieves the tags of a bucket.
- put_bucket_tagging Adds tags to a bucket.
- delete_bucket_tagging Removes all tags from a bucket.
- get_object_tagging Retrieves the tags of an object.
- put_object_tagging Adds tags to an object.
- delete_object_tagging Removes all tags from an object.

Versioning

- get_bucket_versioning Retrieves the versioning configuration of a bucket.
- put_bucket_versioning Enables or disables versioning on a bucket.

Lifecycle Configuration

- get_bucket_lifecycle_configuration Retrieves the lifecycle rules for a bucket.
- put_bucket_lifecycle_configuration Updates lifecycle rules for a bucket.
- delete_bucket_lifecycle Deletes the lifecycle configuration of a bucket.

Replication

- get_bucket_replication Retrieves the replication configuration of a bucket.
- put_bucket_replication Sets up cross-region replication for a bucket.
- delete_bucket_replication Deletes the replication configuration of a bucket.

Encryption

- get_bucket_encryption Retrieves the default encryption configuration of a bucket.
- put_bucket_encryption Sets the default encryption configuration for a bucket.

- delete_bucket_encryption - Removes the default encryption configuration from a bucket.

Notifications

- get_bucket_notification_configuration Retrieves the notification configuration of a bucket.
- put_bucket_notification_configuration Updates the notification configuration of a bucket.

Transfer Acceleration

- get_bucket_accelerate_configuration Retrieves the transfer acceleration state of a bucket.
- put_bucket_accelerate_configuration Enables or disables transfer acceleration for a bucket.

Request Payment Configuration

- get_bucket_request_payment Retrieves the payment configuration of a bucket.
- put_bucket_request_payment Updates the request payment configuration of a bucket.

Object Lock Configuration

- get_object_lock_configuration Retrieves the object lock configuration of a bucket.
- put_object_lock_configuration Updates the object lock configuration of a bucket.
- get_object_retention Retrieves the retention settings of an object.
- put_object_retention Updates the retention settings of an object.
- get_object_legal_hold Retrieves the legal hold status of an object.
- put_object_legal_hold Updates the legal hold status of an object.

Inventory & Metrics

- get_bucket_inventory_configuration Retrieves an inventory configuration for a bucket.
- put_bucket_inventory_configuration Sets an inventory configuration for a bucket.
- delete_bucket_inventory_configuration Deletes an inventory configuration from a bucket.
- list_bucket_inventory_configurations Lists all inventory configurations for a bucket.

Public Access Block Configuration

- get_public_access_block Retrieves the public access block configuration of a bucket.
- put_public_access_block Sets the public access block configuration for a bucket.
- delete_public_access_block Deletes the public access block configuration from a bucket.

Select Object Content (Query CSV/JSON Files in S3)

- select_object_content - Runs a SQL-like query on an object stored in S3.

Advanced Features

- write_get_object_response Writes a response for an object retrieved via S3 Object Lambda.
- restore_object Restores an object from Glacier storage.
- list_bucket_analytics_configurations Lists analytics configurations for a bucket.
- list_bucket_intelligent_tiering_configurations Lists intelligent tiering configurations for a bucket.
- list_bucket_metrics_configurations Lists metrics configurations for a bucket.

Example Syntax

```
s3_client.put_object(
    Bucket='example-bucket',
    Key='example.txt',
    Body=b'Hello, world!'
)
```