1 CheatSheet: Linux Disk LINUX

- PDF Link: cheatsheet-disk-A4.pdf, Category: linux
- Blog URL: `https://cheatsheet.dennyzhang.com/cheatsheet-disk-A4`
- Related posts: CheatSheet: Linux Process, CheatSheet: Linux Networking, #denny-cheatsheets

File me Issues or star this repo.

1.1 Summary

Name	Comment
df	Show information about the file system.
du	Summarize disk usage of each FILE, recursively for directories.
dd	Copy a file, converting and formatting according to the operands.
mount	Mount file systems.
lsblk	List information about all available or the specified block devices.
Reference	CheatSheet: Linux Process, CheatSheet: Linux Networking, CheatSheet: Linux Disk

1.2 du

Name	Comment
Show the disk usage of current folder	`du -sh`
Show disk usage for a given folder	`du -h -d 2 /data/elasticsearch/`
Sort directories/files by size	GitHub: sort-disk-size.sh

1.3 df

Name	Comment
List all disks with humanreadable format	`df -h`

1.4 dd

Name	Comment
Create a file with fixed size and random context	dd if=/dev/urandom of=/tmp/random.txt count=3 bs=256
Create a file with fixed size and empty context	dd if=/dev/zero of=/tmp/random.txt count=3 bs=256

1.5 mount

Name	Comment
Mount an ISO to a folder	`mount -o loop my-disk.iso /mnt/disk`
Mount NFS	`mount -t nfs 192.168.1.1:/usr/share /mnt/share`
Remount rootfs as read-write in repair mode	`mount -o remount,rw /`

1.6 lsblk

Name	Comment
List all available block devices	`lsblk`
List all scsi devices	`lsblk --scsi`
Show a specific device	`lsblk /dev/sda`
List block devices with filesystem info	`lsblk --fs`

1.7 Online Help Usage

```
> du --help
Usage: du [OPTION]... [FILE]...
  or:  du [OPTION]... --files0-from=F
Summarize disk usage of each FILE, recursively for directories.

Mandatory arguments to long options are mandatory for short options too.
  -0, --null            end each output line with 0 byte rather than newline
```

```
  -a, --all             write counts for all files, not just directories
      --apparent-size   print apparent sizes, rather than disk usage; although
                          the apparent size is usually smaller, it may be
                          larger due to holes in ('sparse') files, internal
                          fragmentation, indirect blocks, and the like
  -B, --block-size=SIZE  scale sizes by SIZE before printing them; e.g.,
                           '-BM' prints sizes in units of 1,048,576 bytes;
                           see SIZE format below
  -b, --bytes           equivalent to '--apparent-size --block-size=1'
  -c, --total           produce a grand total
  -D, --dereference-args  dereference only symlinks that are listed on the
                          command line
  -d, --max-depth=N     print the total for a directory (or file, with --all)
                          only if it is N or fewer levels below the command
                          line argument;  --max-depth=0 is the same as
                          --summarize
      --files0-from=F   summarize disk usage of the
                          NUL-terminated file names specified in file F;
                          if F is -, then read names from standard input
  -H                    equivalent to --dereference-args (-D)
  -h, --human-readable  print sizes in human readable format (e.g., 1K 234M 2G)
      --inodes          list inode usage information instead of block usage
  -k                    like --block-size=1K
  -L, --dereference     dereference all symbolic links
  -l, --count-links     count sizes many times if hard linked
  -m                    like --block-size=1M
  -P, --no-dereference  don't follow any symbolic links (this is the default)
  -S, --separate-dirs   for directories do not include size of subdirectories
      --si              like -h, but use powers of 1000 not 1024
  -s, --summarize       display only a total for each argument
  -t, --threshold=SIZE  exclude entries smaller than SIZE if positive,
                          or entries greater than SIZE if negative
      --time            show time of the last modification of any file in the
                          directory, or any of its subdirectories
      --time=WORD       show time as WORD instead of modification time:
                          atime, access, use, ctime or status
      --time-style=STYLE  show times using STYLE, which can be:
                            full-iso, long-iso, iso, or +FORMAT;
                            FORMAT is interpreted like in 'date'
  -X, --exclude-from=FILE  exclude files that match any pattern in FILE
      --exclude=PATTERN    exclude files that match PATTERN
  -x, --one-file-system    skip directories on different file systems
      --help     display this help and exit
      --version  output version information and exit

Display values are in units of the first available SIZE from --block-size,
and the DU_BLOCK_SIZE, BLOCK_SIZE and BLOCKSIZE environment variables.
Otherwise, units default to 1024 bytes (or 512 if POSIXLY_CORRECT is set).

SIZE is an integer and optional unit (example: 10M is 10*1024*1024).  Units
are K, M, G, T, P, E, Z, Y (powers of 1024) or KB, MB, ... (powers of 1000).

GNU coreutils online help: <http://www.gnu.org/software/coreutils/>
For complete documentation, run: info coreutils 'du invocation'
```

1.8 More Resources