

Figure 1 Login Page

In Login Page there are 2 columns

- 1. Username/email
- 2. Password

If user doesn't have an account, the user have to create it in Sign Up page. User entry data as follows:

- Full name
- Username
- 3. Email
- 4. Password (and Re-type)

After user successfully create an account or log in, it will direct to the main page.

For any conditions, if user press back button it will directly close the application





Paket Ayam Timbel - Timbel Farm House

















Figure 2 Main Page

The main page has 3 parts:

1. Quick view

Show some food discount pictures with the location name in bold. If user choose the pictures it will directly go to food that has been chosen. Maximum Food pictures that displayed is 5 pictures

Menu displayed from recommended category.

2. Category

Consist of:

- a. Best seller
- b. Recommended
- c. Limited
- d. Foods &drinks
- e. Entertainment
- f. Shopping

If user press one of the category it will directly go to each category page, except entertainment and shopping it will show "coming soon"

1. Main menu bar

Main menu bar consists of four function

- a. Home
- b. Wallet
- c. Help
- d. User



Paket Avam Timbel - Timbel Farm House



Kue Bulan - Rumah Kong Hok Sid



Figure 3 Coupon Page

Coupon page will display list of coupon that available for each category in main page with the following specification:

- a. Best seller: list of coupon with the most used coupon
- b. Recommended: list of coupon with recommended from admin
- c. Limited: list of limited coupon, less than 20 coupon
- d. Food & Drink: list of coupon with food and drink category

This page contains menu photos including the place. At the top of this page there is back button which, if user press it, will return to main page



Lokasi Review Share

Detail Voucher

Lorem ipsum dolor sit amet, consectetur adipiscing elit, sed do elusmod tempor incididunt ut labere et dolore magna allejau. Ut enim ad minim venium, quis nostrud exercitation ullamco laboris niai ut aliquip ex ea commodo consequat.



Figure 4 Menu Page

The menu page contains detail of available menu.

There is some information in that page divided into two sections, upper and middle.

Information on upper sections:

- a. Promotions name
- b. Merchant's name
- c. The address of merchant or where to use the coupon
- d. Amount of used coupon (If coupon is used, the number is increased. Real-time)
- e. Coupon expire time.

Information on middle sections:
Coupon detail that consists of description.

All of information in this page is input by Admin

At the bottom there is 2 options, there is "Use Coupon" and "Save to Wallet"

- Use Coupon
 If user press this button, then there is a password form to be filled by merchant.
- Save to Wallet
 If user press this button, then coupon will be saved to
 wallet page and only left "Use Coupon" button behind.

Back button on this page will redirect user to the user's previous page.

