

Phase 6: what was built

BeamMP Race Manager Client: dhardesty99

Phase 6 is on the server. It is the last phase of the plan: CoPilot and Chase, the challenges, the language switch and the tracking switch. This is what each part does and how to use it. The build is 0.7.5.

1 CoPilot and Chase

Watch another driver from their car. There are two ways in, and both sides have to agree.

- **Invite.** You are driving and want somebody to ride with you. Open CoPilot, press Invite next to their name. They accept or say no.
- **Ask to watch.** You want to watch a driver. Press Ask to watch next to their name. They accept or say no.

On yes, the watcher's camera goes into the driver's car. The C key changes the camera as usual, so CoPilot is the view from the seat and Chase is the view from behind. The watcher's own car stays where it was parked, and their own timing is not touched.

- Stop watching brings you back to your own car. A driver can also send everybody watching them back with one button.
- The plain TAB switch is shut on the server. A switch onto anybody else's car is undone at once, so watching is by invite or request only.
- Arming a run ends watching, because your own car is the one that races. Somebody mid run cannot be made to watch, and cannot ask to.
- If the driver changes car, the watcher is moved to the new one. If the driver leaves, the watcher is sent home. An offer nobody answers goes away after a minute.

2 Challenges

Daily and weekly time attacks, posted by admins, entered by everybody.

Posting one

Open Challenges and press Post a challenge. Give it a name and a few lines of description, pick daily or weekly, the course, the laps if the course is a circuit, the classes that may enter, and the ladder of times: each rung is a time to beat and the XP it pays, typed as 1:32.43 or 92.43. Up to twenty rungs. Pick when it starts: now, in one hour, in six, or tomorrow. A daily runs for a day from its start, a weekly for seven days.

Three daily and five weekly challenges can be open at once. Ending one, or one running out, makes room. Edit changes any of it live; a change of course or laps clears its board, because those times were driven on the old one. End it now and Delete are there too.

Entering one

The board shows daily challenges in one table and weekly in another, each a set size that scrolls. Under each name, in grey, the classes and the course. Click a challenge and the window opens out

with everything about it: the description, the course and laps, the classes, when it ends, the ladder, your best time, and the board of everyone who has finished it. Pick your class if it asks for one, controller or wheel, and press Enter and go to the grid. From there it is a normal run.

Scoring

Your best time on each challenge is kept. Finishing under a rung pays that rung's XP, once. A faster run later pays only the difference up to the higher rung. A slower run changes nothing. A time outside the ladder still goes on the board. The results row of the run says which rung you reached and what it paid.

- Teams cannot enter a challenge. Break up the team first.
- Guests count, the same as everybody.
- A challenge that is over stays on the board a while, greyed, so the times can still be read.

3 Options

- **Language.** English or Spanish. The bars, the window titles and the CoPilot and Challenges windows change. The rest stays in English.
- **XP and challenge tracking.** On or off for yourself. Off means a run counts for nothing: no XP, no challenge time. It is for practice. Turn it back on before a race.

4 Guests and accounts

Everybody on the server counts, guest or not: a name picked once, a level, records, XP and challenges. A guest is recognised on the next visit by their connection, and the six character code from the first join brings their name back if that ever changes.

Whether guests may join at all follows Bobby's file on the server, `Resources/Server/PatreonAuth/allowed_discord`. While its `enabled` is false, guests join as normal. When Bobby switches it on, a guest is turned away at the door with a message to log in with a BeamMP account, and accounts still get in. The file is read every ten seconds, so the switch works live. On the console, `rm guests` says the current state. Note that anyone who joins as a guest, including yourself, is turned away while it is on.

Somebody logged into a BeamMP account is named after their account on first join, with no card to fill in, as long as that name is one the server can take and nobody has it. Names already picked are never replaced.

5 Discord

The Open in browser button goes through the BeamMP launcher, which opens the link in your browser. The game keeps focus, so Alt-Tab to it. Copy link is still there.

6 The console

<code>rm challenges</code>	the challenges on the board
<code>rm challenge end <id></code>	end a challenge now
<code>rm challenge delete <id></code>	take a challenge off the board
<code>rm watching</code>	who is watching whom
<code>rm guests</code>	whether guests may join, and where that is decided

7 Testing

Every part of phase 6 runs against the same test host as the earlier phases, without the game. The watching flow, the challenge board, the ladder, the limits, the schedule, the tracking switch, guests and accounts, and the camera side in the car are all covered: 166 checks in three new suites, and every earlier suite still passes. The interface is audited for the mistakes that only show in the game, and each fix was checked against a broken version to be sure the test would catch it.