```
*& Report ZCAP_BAPI_MATERIAL_UPLOAD
REPORT ZCAP_BAPI_MATERIAL_UPLOAD LINE-SIZE 800.
INCLUDE ZCAP_BAPI_MATERIAL_UPLOAD_INCL. " Include Program
SELECTION-SCREEN BEGIN OF BLOCK B1 WITH FRAME TITLE TEXT-001.
PARAMETERS P_FILE TYPE RLGRAP-FILENAME. "Local file for upload
SELECTION-SCREEN END OF BLOCK B1.
AT SELECTION-SCREEN ON VALUE-REQUEST FOR P_FILE. " validation for Value Request
 CALL FUNCTION 'F4_FILENAME'
   EXPORTING
     PROGRAM_NAME = SYST-CPROG
     DYNPRO_NUMBER = SYST-DYNNR
    IMPORTING
     FILE\_NAME = P\_FILE.
START-OF-SELECTION.
DATA P_FILE1 TYPE STRING.
     P\_FILE1 = P\_FILE.
 CALL FUNCTION 'GUI_UPLOAD' " Upload for Data Provider
   EXPORTING
     FILETYPE = P_FILE1
     HAS\_FIELD\_SEPARATOR = 'X'
   TABLES
     DATA\_TAB = IT\_TAB1.
 LOOP AT IT_TAB1 INTO WA_TAB1.
   BAPIMATHEAD-MATERIAL = WA\_TAB1-MATNR.
   BAPIMATHEAD-IND_SECTOR = WA_TAB1-MBRSH.
    BAPIMATHEAD-MATL\_TYPE = WA\_TAB1-MTART.
   BAPIMATHEAD-BASIC\_VIEW = 'X'.
   BAPI\_MARA-MATL\_GROUP = WA\_TAB1-MATKL.
   BAPI_MARA-BASE_UOM
                         = WA\_TAB1-MEINS.
   BAPI\_MARAX-MATL\_GROUP = 'X'.
                          = 'X'.
   BAPI_MARAX-BASE_UOM
   WA_TAB2-LANGU
                    = 'E'.
   WA\_TAB2-MATL\_DESC = WA\_TAB1-MAKTX.
   APPEND WA_TAB2 TO IT_TAB2.
   CALL FUNCTION 'BAPI_MATERIAL_SAVEDATA' " Calling RFC Function Module for Create and Change
                                         " Material Master Data for MM01 and MM02 T-codes.
     EXPORTING
                          = BAPIMATHEAD
       HEADDATA
       CLIENTDATA
                          = BAPI_MARA
                          = BAPI_MARAX
       CLIENTDATAX
       PLANTDATA
                          = BAPI\_MARC
        PLANTDATAX
                          = BAPI_MARCX
```

```
IMPORTING
                 = IT_RETURN
     RETURN
   TABLES
     MATERIALDESCRIPTION = IT_TAB2.
                             " Return Parameters displayed for BAPI Status
 WRITE : / IT_RETURN-TYPE,
         3 IT_RETURN-ID,
         23 IT_RETURN-NUMBER,
         25 IT_RETURN-MESSAGE,
           IT_RETURN-LOG_NO,
            IT_RETURN-MESSAGE_V1,
            IT_RETURN-MESSAGE_V2,
            IT_RETURN-MESSAGE_V3,
            IT_RETURN-MESSAGE_V4,
            IT_RETURN-PARAMETER,
            IT\_RETURN-ROW ,
            IT_RETURN-FIELD.
ENDLOOP.
```