MY SITUATION ROOM

Platform Administrator Manual

Election observation & real-time collation

An AI Brains Ventures production

This is the guide for **you, the platform owner** (AI Brains Ventures). Your account is the **platform administrator**: the only role that can create and control **Command Centres** (the top-level accounts you hand to clients). Each client then runs their own Command Centre, creates their own Situation Rooms, and their observers report from the field — all sealed off from every other client.

> Audience separation: you create and switch Command Centres on and off. You **cannot** see any client's rooms, observers, results, photos or audit — that isolation is enforced in the database, by design, for trust. You hand each client the keys to their own house; you don't live in it.

---

0. The three levels at a glance

Level	Who	Logs in at	Creates
Command Centre	A client organisation (e.g. a party, an observer group)	`/command/`	Situation Rooms + operators
Situation Room	An LGA / area supervisor	`/room/`	Observer codes
Observer	A field agent at a polling unit	the Android app or `/observer/`	reports (video, GPS, tallies, EC8A)

You operate at the very top: you create the **Command Centres** themselves.

---

1. Signing in as the administrator

1. Open `https://mysituationroom.com.ng/command/`.
2. Enter your **operator name** (`admin`) and **passcode**.
   - On a brand-new server the first passcode is printed **once** in the server log at first boot (or set by `COMMAND_PASSCODE`). Change it immediately (section 7).
3. If you turned on **two-step login**, enter the 6-digit code from your authenticator app.

You land in the **Main Command Centre**. Because you are the administrator you also see three extra tabs the clients never see: **Command Centres**, **Marketing**, and **Locations**.

---

2. Creating a Command Centre for a client

This is your main job. Go to the **Command Centres** tab.

1. Under **New Command Centre**:
   - **Name** — the client's name, e.g. `Kano State Command` or `Blue Party National`.
   - **State (optional)** — pick one to auto-fill that state's LGAs, wards and polling units for the client. Leave blank for a multi-state client.
   - **First operator name** — *leave blank* and the system makes a unique one from the name (`kano-state-command`, then `-2` if taken). Type one only if you want a specific login name; it must be unique across the whole platform.

- **Operator passcode / Confirm** — *leave blank* to auto-generate a strong one, or type your own (min 8 characters) and confirm it. Use **Show** to check what you typed.

2. Click **Create Command Centre**.
3. A **sign-in card with a QR code** pops up (Copy / Print), and a ready-to-send invite is copied to your clipboard, e.g.:

```
Kano State Command — My Situation Room
Login: https://mysituationroom.com.ng/command/
Operator: kano-state-command
Passcode: REY4YXQDAM
Open the link, choose "Command Centre", and sign in...
```

4. **Send that to the client** (WhatsApp, email), or print the card. They can type the operator name and passcode, or simply **scan the QR** to sign in. That's everything they need to start.

Re-sending or resetting a client's login

On the client's row in the **Command Centres** list, click **Share**. This **sets a fresh passcode** (the old one stops working) and copies a new invite to send. Use it if a client lost their passcode or you suspect it leaked.

Turning a Command Centre off / on

On the client's row, click **Disable (suspends its rooms)**. The client can no longer log in and all their Situation Rooms are suspended — use this at the end of an engagement or for non-payment. Click **Enable** to switch it back on. You cannot disable your own (`CC-MAIN`).

> **Deleting:** there is deliberately no one-click "delete a Command Centre" button, so a client's election record is never wiped by accident. Disabling is the safe, reversible equivalent. If a client must be permanently removed, do it on the server with a database operation and a backup first — ask your engineer.

---

3. Loading the location data (states → LGAs → wards → PUs)

Clients pick polling units from this list, so it must be loaded. **Locations** tab:

- **Fetch for a state** — choose a state and pull its official breakdown automatically.
- **Import a file** — upload an Excel/CSV of `state, lga, ward, pu` if you have your own dataset.
- You'll see counts per state once loaded.

Do this once per state you operate in. When you set a state on a Command Centre (section 2), that client is scoped to it automatically.

---

4. Marketing & link tracking (your sales tool)

The **Marketing** tab is yours alone — it drives client acquisition.

- **Tracking links** — type a label (e.g. `inec-kano`, `whatsapp-batch-1`) and copy the generated `…/pitch?ref=<label>` link. Share a different label with each person/channel.
- **Opens** — total opens, unique visitors, today, by label and by day.
- **Devices & browsers** — what people viewed on, and where they came from.
- **Leads & contacts** — people who filled the **Request a demo** form on the pitch page (name, phone, organisation), each a click-to-WhatsApp link, with CSV export.

> A web page **cannot** read a visitor's phone number — no browser allows it. The Leads list shows people who *chose* to leave their details or who messaged your WhatsApp.

The public pitch page itself is at `/pitch` and the demo button opens your WhatsApp (+234 803 254 0215).

---

5. Your own live demo (for prospects)

See `DEMO-GUIDE.md`. In short: run the system, `npm run seed:demo` fills a believable Kano election ("Kano State Command (Demo)") you can walk a client through, and re-running it resets the demo. It never touches real client data.

---

6. The Android apps

Two apps are built by CI and published on the landing page automatically:

- **Observer app** — `/download/app`
- **Situation Room app** — `/download/room`

Both also run in any browser. You don't build these by hand — a push that changes the app rebuilds them (see `mobile/README.md`). On the landing page each shows a **Download (.apk)** button and a QR code once built.

---

7. Securing your own account

App Settings tab:

- **Change your passcode** — do this on day one; use a long, unique one.
- **Two-step login (TOTP)** — enable it and scan the QR with Google Authenticator / Authy. After this, every login needs the 6-digit code. Strongly recommended for the administrator.
- **App name** — the platform name shown on login screens.
- **Add operators** — you can add more administrator-side operators if needed; each gets their own name + passcode and (optionally) their own two-step login. Disable or reset any of them here.
- If an operator loses their phone, you can **clear their two-step login** so they can set it up again on a new device.

See `SECURITY.md` for the full checklist (branch protection, firewall, backups, 2FA).

7a. Help tab

The **Help** tab shows both manuals inside the app — this one (visible to you only) and the client operator manual — each with a **Download PDF** button, handy for onboarding emails.

8. Audit log

Audit Log tab records every significant action with a timestamp — logins, Command Centre creation, passcode resets, and more. It's your record of who did what. (Each client has their own, separate audit log inside their own Command Centre.)

9. Live field video — what to tell clients

If a client asks "can two of us watch the same observer at once?" — **yes**. The observer's phone streams once and everyone authorised in that command/room sees the same live feed simultaneously, can talk back, and can push it to an external broadcast via **Restream**. Nothing extra to configure as long as LiveKit is running (it is, in the standard deployment). For people **outside** the client's team, the client uses **Share Live View**: a view-only page (collation, map, video, optional talk-back) opened with a link and a passcode — see the operator manual, section 5a.

10. Quick reference — what only YOU can do

- Create / name Command Centres and assign a state.
- Generate and re-issue client login invites (Share).
- Enable / disable a client's Command Centre.
- Load location datasets for new states.
- See platform-wide Marketing and Leads.
- Set the platform name and your own security.

Everything *inside* a Command Centre — rooms, observers, results — is the client's to run, with the operator guide below.