Ledgerline Payables User Manual

Document	LL-AP
Version	v4.2
Effective from	15 August 2026
Owner	Ledgerline vendor
Approved by	Northbridge IT
Status	Approved

1. Introduction

1.1 Who this manual is for

This manual is for accounts payable, purchasing and finance users of the Ledgerline payables module.

1.2 Screens covered

The payables screens are FIN-AP-01 (invoice entry), FIN-AP-03 (hold queue) and FIN-AP-05 (payment proposal and run). The assistant, Ask Northbridge, uses the same screens through the service layer.

2. Signing in

Each user signs in with their own account. Approvals are recorded under the name of the user who signs in.

3. FIN-AP-01 Invoice entry

3.1 Entering an invoice

Select the supplier first, then the purchase order. Ledgerline copies the order lines and the goods receipt, and runs the price, quantity and duplicate checks when the invoice is saved.

3.2 Fields on FIN-AP-01

Field	Meaning	Rule
Supplier Invoice No.	The supplier's own invoice number	Takes at most 16 characters
IRN	E-invoice reference number	Checked against the e-invoice portal
TDS Section	Section under which TDS is deducted	New-Act code, for example 393(1)-8(ii)
Hold Code	Why the invoice is held	H-PRC, H-QTY, H-DUP or H-BNK

On FIN-AP-01 the field Supplier Invoice No. takes at most 16 characters. On FIN-AP-01 the field TDS Section takes the new-Act code, for example 393(1)-8(ii).

4. FIN-AP-03 Hold queue

The hold queue lists every held invoice with its hold code and the date it was held. Only a user allowed by the Approval Matrix sees the Release button.

5. FIN-AP-05 Payment proposal and run

5.1 Building a proposal

FIN-AP-05 proposes every approved invoice due in or before the selected run. Payments that need further approval are blocked until it is given.

5.2 Payment status codes

Code	Meaning
SCH	scheduled
PK	parked
SNT	sent to bank
CNF	confirmed by the bank statement

A payment with status PK is parked: it is not in the run and will not be paid until the block is cleared. A parked payment can look scheduled on the proposal list; always read the status code.

6. Messages

Error messages and their codes are listed in the LL-ERR Error Code Reference.