Lab Assignment on Unit V

Aim: Write a program to demonstrate subletting and find the subnet masks.

Requirements: Fedora 20 with Pentium IV and above, 1 GB RAM, 120 G.B HDD, Monitor, Keyboard, Mouse, Modelio, Eclipse, CDT, Python interpreter, Pydev, J2SE

Theory:

1. Subletting

Subletting is when you enter a lease with someone else, known as a subtenant, for an apartment or other property which you already rent. Subletting is usually used when you're renting a property and need to leave the property before the lease is up and don't want to spend the money to continue renting the property which you don't inhabit. Subletting lets you essentially act as a sort of mini-landlord for the property you were renting to keep yourself from paying for something you're not using.

2. Netmask

A netmask is a 32-bit mask used to divide an IP address into subnets and specify the network's available hosts. In a netmask, two bits_are always automatically assigned. For example, in 255.255.225.0, "0" is the assigned network address. In 255.255.255.255, "255" is the assigned broadcast address. The 0 and 255 are always assigned and cannot be used.

Below is an example of a netmask and an example of its binary conversion.

Netmask:	255.	255.	255.	255
Binary:	11111111	11111111	11111111	11111111
Netmask length	8	16	24	32

Counting out the bits in the binary conversion allows you to determine the netmask length. Above is an example of a 32-bit address. However, this address is a broadcast address and does not allow any hosts (computers or other network devices) to be connected to it.

A commonly used netmask is a 24-bit netmask, as seen below.

Netmask:	255.	255.	255.	0
Binary:	11111111	11111111	11111111	00000000
Netmask length	8	16	24	

Using a 24-bit netmask, the network would be capable of 2,097,150 networks or 254 different hosts with an IP range of 192.0.1.x to 223.255.254.x, which is usually more than enough addresses for one network.

A simple formula can be used to determine the capable amount of networks a netmask can support.

$$2 \wedge (\text{netmask length -# of used segment}) - 2$$

For example, if we used a netmask length of 24, having a netmask of 255.255.255.0 with 3 used segments, subtract 3 from the netmask length, e.g. 24-3=21. With this number determined, plug it into the above formula to get $2^{^{21}}$ - 2=2,097,150 total number of networks. You are subtracting 2 from this number because of the broadcast and network addresses that are already being used.

Another example is a netmask length of 16, having a netmask of 255.255.0.0 with 2 used segments. Using the above formula, you would get $2^{^{14}}$ - 2 = 16,382 total number of networks.

To determine the amount of hosts a netmask is capable of supporting, use the following formula. $2^{\Lambda^{(\# \text{ of zeros})}} - 2$

For example, with a netmask length of 24, as shown in the above chart, there are 8 zeroes. Therefore, using the formula above, this would be 2^{8} - 2 = 254 total number of hosts. Again, 2 is subtracted from this number to account for the broadcast and network addresses.

Again, another example of a netmask length of 16, there would be 16 zeroes. The formula in this case would be 2^{16} - 2 = 65,534 total number of hosts.

Below is a breakdown of each of the commonly used network classes.

Class	Netmask length	# of networks	# of hosts	Netmask
Class A	8	126	16,777,214	255.0.0.0
Class B	16	16,382	65,534	255.255.0.0
Class C	24	2,097,150	254	255.255.255.0

3. Subnet Masks

Subnet mask is a mask used to determine what subnet an IP address belongs to. An IP address has two components, the network address and the host address. For example, consider the IP address 150.215.017.009. Assuming this is part of a Class B network, the first two numbers (150.215) represent the Class B network address, and the second two numbers (017.009) identify a particular host on this network.

Short for **subnetwork mask**, a **subnet mask** is data used for bitwise operations on a network of IP addresses that has been divided into two or more groups. This process, known as **subnetting**, divides an IP network into blocks of logical addresses. Subnetting can improve security and help to balance overall network traffic. A common example of a subnet mask for class C IP addresses is 255.255.255.0, the default subnet mask for many computers and network routers. When applied to **subnet**, a subnet mask shows the routing prefix.

Subnetting enables the network administrator to further divide the host part of the address into two or more subnets. In this case, a part of the host address is reserved to identify the particular subnet. This is easier to see if we show the IP address in binary format.

The full address is:

10010110.11010111.00010001.00001001

The Class B network part is:

10010110.11010111

The host address is:

00010001.00001001

If this network is divided into 14 subnets, however, then the first 4 bits of the host address (0001) are reserved for identifying the subnet.

Subnet Mask	255.255.240.000	11111111.11111111.11110000.00000000		
IP Address	150.215.017.009	10010110.11010111.00010001.00001001		
Subnet Address	150.215.016.000	10010110.11010111.00010000.00000000		
The subject address, therefore, is 1EO 21E 016 000				

The subnet address, therefore, is 150.215.016.000.

Outcomes:

The output will be the subnet mask of the given IP address of the host.