

1 Stock Monitoring

Summary

Menu	Material management → Inventory management → Stock monitoring
Transaction code	stomo
Function authorization	stomo

Usage

Stock monitoring allows to display those materials (batches), for which the [inventory limits](#) are exceeded or not reached in a [material buffer](#).

Integration

Since these material buffers can have different sizes and since the definition of when such a material buffer is full depends on the size of the material, the definition of the inventory limits to be monitored is referred to a material and to a [material buffer](#). This creates the possibility to monitor only critical materials and/or only certain material buffers.

All materials per material buffer that match the entered selection criteria and for which [inventory limits](#) were defined for the respective material buffer will be shown in this list that updates cyclically. To do so, the existing batches will be cumulated to the material number and be displayed. To further limit this, only batches of a specific status can be used.

Requirements

The following requirements must be met to display materials in stock monitoring:

1. In the configuration (menu: *Master data > Material > Inventory limits*) you must have defined corresponding inventory limits for the [combination of material and material buffer](#).
2. The [material buffer](#) (menu: *Master data > Material > Material buffer*) must not be a hierarchical buffer. In addition the indicator "include in stock" must be set.

Selection criteria

The following selection criteria are available in the application:

Material buffer

This selection criterion refers to the material buffer of the material. All materials with the selected [material buffer](#) will be shown.

Material

Any stock with the selected material will be shown.

Batch status

This selection criterion refers to the batch status of the stocks. All materials with the selected batch status will be shown.

If several selection criteria are used, the intersection of the selection criteria will be shown.

Field descriptions

Fill level

Symbol	Symbol color	Meaning	Meaning related to the configured inventory limits
	green	Stock o.k.	Stock between min. warning stock level and max. warning stock level.
	yellow	Stock below warning limit	Stock between min. warning stock level and minimum stock.
	red	Stock below alarm limit	Stock between min. alarm quantity and min. warning stock level
	red	Stock below minimum	Stock below minimum stock
	yellow	Stock above warning limit	Stock between max. warning stock level and max. alarm quantity.
	red	Stock above alarm limit	Stock between max. alarm quantity and max. stock level
	red	Stock above maximum	Stock above max. stock level

Material type

Assigned material type of the material

Material

Material number

Material designation

Designation of the material

Quantity

Stock quantity of the material

Unit

Quantity unit

Material buffer

Assigned material buffer of the material

Designation

Designation of the material buffer

Company

Assigned company to the material buffer

Department

Assigned department to the material buffer

Area

Assigned area to the material buffer

Cost center

Assigned cost center to the material buffer

Storage location

Assigned storage location to the material buffer

Type

Type of the material buffer

Min. stock quantity

Defined min. stock quantity of the material in this material buffer

Lower alarm limit (min. alarm quantity)

Defined min. alarm quantity of the material in this material buffer

Lower warning limit (min. warning stock level)

Defined lower warning stock level of the material in this material buffer

Upper warning limit (max. warning stock level)

Defined upper warning stock level of the material in this material buffer

Upper alarm limit (max. alarm quantity)

Defined upper alarm quantity of the material in this material buffer

Max. stock level

Defined max. stock level of the material in this material buffer