

1 AIP Batch Merge

Summary

In production partly consumed containers with the same material are often combined to one container. However, the system considers the materials to be located in different batches. With this function the terminal provides an opportunity to merge batches and to print a label for the new batch.

Usage

At the moment, it is impossible to:

- combine "normal" batches with merged batches and/or serial numbers
- combine merged batches and serial numbers or to add several serial numbers to one merged batch. The merged batch number including the serial number always has to be entered.
- combine individual serial numbers into one merged batch. Their merged batch number always has to be entered. It is also possible to use the standard function "collection of serial numbers" A_SNR with the relevant configuration.

Prerequisite

The relevant configuration has to be made to be able to use this function.


Terminal functions

The function is triggered manually by using the key of the "merge batches" dialog (BATCH_MERGE).



If the terminal is offline, only a limited number of posting functions is provided based on the available data. If the terminal is offline, errors are not displayed e.g. if posting failed on the server.

Dialog



Description of display fields:

- **Batch**
Batch number to be entered by the user (manually/by scanning)
- **Generate new batch number / involved batch number**
Specifies whether the new batch is to be generated with a new batch number or if an involved batch number is used for the new batch. If an involved batch number is used, this one has to be entered.
- **List of recorded batches**
Shows the entered batches that are to be merged.

Procedure for the "merge batches" function:

- The user opens the "merge batches" dialog by the relevant function key in the basic screen of the terminal
- In the "batch" field the user enters the affected batches (manually or by scanning) he/she wants to merge. Data may be entered manually or by scanning. If batches are entered manually, the input will be confirmed after each batch by . This empties the field for the next input.
- The user specifies whether the new batch is to be generated with a new batch number or if an involved batch number is used for the new batch. If an involved batch number is used, this one has to be entered.
- The "list of recorded batches" shows the batches the user has already entered and wants to merge.

- The user applies the "complete" key. Then the "batch" field and the "list of recorded batches" are emptied. The user receives an intermediate message with the generated batch number for the merged batch. Additional batches may be merged.
- The dialog remains opened until the user closes it explicitly by pressing "cancel". Then batches are merged into a new batch.
- A label can be printed for the merged (new) batch.

Function keys

- **Function key "cancel"**
This function key rejects the entered data and/or empties the result list. New data may be entered. The dialog remains open.
- **Function key "complete"**
Entered batches are merged into one batch. By using this function key, the dialog is emptied (i.e. no data included) and the new batch (batch number) is shown on the terminal. A label is printed subject to configuration.
- **Function key "reject"**
Entered batches are not merged into one batch. The data input is rejected.
- **Function key "additional data"**
Subject to configuration, this function leads to the next workflow to record attributes and/or document links.

Result

- **By the "cancel" function**
The dialog remains open. All entered data are rejected. The input data are not posted. Data input can be restarted.
- **By the "complete" function**
This function key closes the dialog. Entered batches are merged into one batch and data are posted accordingly. The amount of merged batches is reduced accordingly and set to the "processed" batch status. The new batch includes the merged amount. If merged batches are combined, the serial numbers will be assigned to the new merged batch. Label printing may be triggered by this.
- **By the "enter" function**
Entered data are recorded for each batch but not yet posted.
This function key records the individual batches once they have been entered and displays them in the result list. The dialog remains open.
- **By the "additional data" function**

Similar to the output batch change, it is possible enter attributes and document links for each combined batch/merged batch. If they are configured, relevant workflows are integrated for data collection. Attributes and document links from previous batches are not taken over.

This dialog does not allow entering attributes/document links for individual serial numbers/sub-batches pertaining to the merged batch.



In addition, the event is also shown in the batch history (old batches and new batch and old merged batches and new merged batch and serial number).

The graphic/tabular overview shows which batches have been merged into one batch.