

1 Assignment Material - Material Type

Overview

Menu	Master data → Material → Material assignment - Material type
Transaction code	asmm
Function authorization	asmm

Usage

This function is used to assign the appropriate [material type](#) to a material in the system.

Integration

Each material can be assigned to a [material type](#). The assignment is used

- if a goods receipt batch is recorded manually
- if an unknown batch is defined

Requirement

The [material type](#) must be defined in the system.

Selection criteria

The following selection criteria are available in the application:

Material

Only the selected materials are selected.

Material type

Only materials with the selected [material type](#) are selected.

When using multiple selection criteria - if nothing else is specified - the amount of overlap of the selection criteria is displayed.

Field descriptions

Material

Material number that is to be assigned to the [material type](#).

Material type

Assigned material type. This must be defined in the system.

Comment

Additional text regarding the material, comments

Min. storage time

Minimum storage time for the material type

During batch determination, the corresponding availability date is calculated using this value (by adding it to the date of manufacture). Up to that point, a batch remains in "Min. storage time" status and cannot be registered.

Please note: this setting overrides the setting with the same name in the *Material type* configuration.

Warning limit

Warning limit of the material type

During batch determination, the corresponding warning date is calculated using this value (by adding it to the date of manufacture). This can be used for an evaluation, e.g. using the function *Warning report*.

Please note: this setting overrides the setting with the same name in the *Material type* configuration.

Expiry limit

Expiry limit of the material type

During batch determination, the corresponding expiry date is calculated using this value (by adding it to the date of manufacture). At this point in time the batch is automatically set to "Expired" status, so it can no longer be registered.

this setting overrides the setting with the same name in the *Material type* configuration.

Notes

A material can only be assigned to exactly one [material type](#). However, one material type can be assigned several materials. The saving procedure for material is case sensitive. The so-called wildcards "*" and "?" can be used in the material field. The selected material type must exist during creation. Otherwise, the creation will be refused.

If a material is assigned to another material type, the material type is NOT automatically updated

- for existing orders/operations
- for existing component lists
- in the existing batches