

1 Multilingual Database Contents

Overview

This document describes how the multilingual display of user data (master data) is processed.

- In addition to the native language of database contents, multilingual designations of master data (e.g. machine designations, status texts, ...) can be managed in MW 3.0.
- The **terminal** requests the texts in the language that is configured for the terminal. This makes it possible not only to operate a terminal on a German system, e.g. in England, with an English-language GUI, but also to display the important names from the database in English.
- Just as is the case for the terminal, these multilingual texts may also be displayed **and edited** using the MES Operation Center.
- It is possible to activate up to 8 languages at the same time which are supported by HYDRA-MW 3.0.
- There are no restrictions as regards the languages that can be displayed for clients that are compatible with Unicode.
- The Windows terminal can also display East Asian languages. (*1)
- Multi-lingual master data can be edited using the System Text Configurator (STC). This means that a simple translation is possible.
- HYDRA partially also delivers initial data that include texts in the native column. These texts have to be translated by way of STC.

(*1) Since English is a language without umlauts and all character sets display the Latin alphabet, English is available for all language configurations.

Available languages

At the moment MESWeaver 3.0 supports the languages listed in the following paragraph for which the "multilingual database contents" functions can also be provided:

- German

- English
- Dutch
- French
- Danish
- Czech
- Spanish
- Portuguese
- Bulgarian
- Polish
- Slovenian
- Hungarian
- Slovak
- Romanian
- Chinese, Simplified
- Italian
- Russian
- Serbian, Cyrillic
- Swedish
- Norwegian
- Croatian
- Japanese
- Korean

Activation

The multilingual database content functions are generally available (short: MDBI). The languages concerned that are to support the MDBI function have to be prepared and activated explicitly by MPDV Implementing.

Functions

In addition to the native language of database contents, MW 3.0 allows for multilingual designations of master data (e.g. machine designations, status texts, ...) to be managed. These multilingual master data may be administered and translated via the system text configurator (STC). If the required language is prepared (configured, activated and translated) for MDBI access to language-specific master data is activated and represented when the clients are started (or when languages are switched at the console).

Administration table

Active and inactive MDBI languages are managed in the **hyd_languages** table. Here, the required configurations are defined.

Only MPDV Implementation is responsible for managing the languages (activation/deactivation).

Schema

Field name	Type	Size	Description
language_id	smallint	-	Unique language index e.g. 6 for Czech
language_iso	char	2	Language key according to ISO code 639 e.g. "cs" for Czech
language_ui	char	10	Language of the user interface e.g. "cs-CZ" for Czech
language_cp	char	6	Windows codepage of the language e.g. 1250 for Eastern European
language_ml	char	80	Multilingual language designation (English), e.g. "Czech" for Czech
language_name	char	80	Language-specific designation in the character set of the respective language e.g. "Česky" for Czech
active	char	1	Y ... activated N ... deactivated (by default) → "This field is configured by MPDV during implementation/customization and must not be changed manually."
sbcs	char	1	Single Byte Character Set Y/N
language_def	smallint	-	Language index of the default language

Index:

create unique index ix_langid on hyd_languages (language_id);

Default configuration

The following MDBI configuration is created when the HYDRA database is being built:

ID	ISO	CP	ML	ACTIVE	SBCS	DEF
01	de	1252	German	N	Y	00
02	en	1252	English	N	Y	00
03	nl	1252	Dutch	N	Y	02
04	fr	1252	French	N	Y	02
05	da	1252	Danish	N	Y	02
06	cs	1250	Czech	N	Y	02
07	es	1252	Spanish	N	Y	02
08	pt	1252	Portuguese	N	Y	02
09	bg	1250	Bulgarian	N	Y	02
10	pl	1250	Polish	N	Y	02
11	sl	1250	Slovenian	N	Y	02
12	hu	1250	Hungarian	N	Y	02
13	sk	1250	Slovak	N	Y	02
14	ro	1250	Romanian	N	Y	02
15	zh	936	Chinese, Simplified	N	N	02
17	it	1252	Italian	N	Y	02
18	ru	1251	Russian	N	Y	02
19	sr	1251	Serbian, Cyrillic	N	Y	02
20	sv	1252	swedish	N	Y	02
21	no	1252	Norwegian	N	Y	02
22	hr	1250	Croatian	N	Y	02
23	ja	932	Japanese	N	N	02
24	ko	949	Korean	N	N	02

MPDV changes this configuration during the implementation process according to the customer's requirements..

Implementing of MDBI functions

MPDV activates the steps required to support MDBI functions during implementing.

→Overview of multilingual columns

The following table shows the supported table columns for which MDBI functions are available:

Implementation	Comment
HR Multilingual configuration of account designations	Accounts are displayed in the corresponding language (terminal info, time sheet, account lists)
HR Multilingual configuration of the designation of remuneration day types	Designations are displayed in the corresponding language (time sheet, personnel scheduling)

HR Multilingual configuration of the designation of absence reasons	Designations are displayed in the corresponding language (display of latest clockings at the terminal, absence reason list)	
PEP Multilingual configuration of qualification designations	Designations are displayed in the corresponding language (HYDRA-PEP on user interface, personnel schedule is displayed on the terminal):	
HYD Designation of units	• Configuration of units • No other dialogs in which the designation is displayed (only the abbreviation is displayed)	
MDE Workplace configuration: Designation, comment	• Workplace configuration • Designations are displayed on the console ○	
MDE Designation of machine status texts	• Configuration • The designation is displayed in the corresponding language ○ Machine overview ○ Machine overview: combo box ○ Order overview ○ Machine status log ○ Event maintenance ○ Status/Status classes/RPA ○ Status/Status classes/RPA: Combobox ○ • Terminal display	
MDE Designation of status classes	• Configuration • The designation is displayed in the corresponding language	

	○ Machine overview ○ Order overview ○ Machine status log ○ Maintenance of postings ○ Event maintenance ○ Downtimes of one/several machines	
BDE Designation of resource performance accounts	• Multilingual configuration of account designations and abbreviations • The designation is displayed in the corresponding language ○ MDE: Status/Status classes/RPA: all tabs ○ MDE: Status/status classes/RPA: RPA profile (column heading) ○ ADE: versatile dialogs (column headings)	
BDE Designation of order status texts	• Multilingual configuration of the designation of order status texts • The designation is displayed in the corresponding language ○ ADE: versatile combo boxes (e.g. order overview, schedule violations, ...) ○ ADE: Order overview: list ○ ADE: Order information ○ ADE: Change status ○ ADE: AVG	
BDE: Designation of reason texts	• Multilingual configuration of reason text designations (deviation reasons, scrap reasons, problem quantity reason, rework reason) • The designation is displayed in the corresponding language	

	○ Scrap statistic based on orders/machines ○ Article statistics ○ Maintenance of postings ○ Event maintenance • Terminal display	
BDE Order type designation	• Multilingual configuration of order type designations • Designations are displayed in the corresponding language in HYDRA-ADE (e.g. order overview, schedule violations)	
WRM Resource type	• Multilingual configuration of resource type descriptions • Designations are displayed in the corresponding language (resource status, resource information, maintenance of resource documents, resource history) • Terminal display	
WRM Resource families	• Multilingual configuration of resource family descriptions • Displayed in versatile evaluations/reports on the console • Terminal display	
WRM Measures	• Multilingual configuration of designations of measures, descriptions and comments • Displayed in versatile evaluations/reports on the console • Entry function of measures on the console • Terminal display	

WRM Designation of status assignment	• Multilingual configuration of the designation of status assignments • Display of the designation in the respective language (resource status, maintenance of resource documents) • Terminal display	
WRM Maintenances	• Multilingual configuration of maintenance designations as well as comments • Display in versatile evaluations on the console, among other things, the machine history, resource history, maintenance	
MPL Material types	• Multilingual configuration of the designation • Displayed in versatile evaluations/reports on the console	
MPL/WRM Material buffers/storage locations	• Multilingual configuration of material buffer designations • Displayed in versatile evaluations/reports on the console • Terminal display	
MPL Transport units	• Multilingual configuration of the designations of transport units	
MPL Material type designation	• Multilingual configuration of material type designations • Designations are displayed in the corresponding language (batch data overview, batch data maintenance)	
MPL Designation of material attributes	• Multilingual configuration of material attribute designations • Designations are displayed in the corresponding language (batch	

	data overview, batch data maintenance)	
CAQ Short designation of statuses	• Displayed in many HYDRA-CAQ search dialogs	
CAQ Detailed designation of HYDRA-CAQ statuses	• Displayed in many master data catalogs • Displayed in nearly all dialogs in the "areas" menu item • Display in evaluations/reports	
CAQ Short designation of the area	• Short designation of HYDRA-CAQ areas	
CAQ Detailed designation of the area	• Display in the terminal configuration of the CAQ tab • Display in inspection planning • Inspection requirements/calibration • In all evaluations/reports	
Detailed designations of HYDRA-CAQ status types	• Initial sample inspection	
CAQ Designation of forms	• Displayed in master data, forms • Displayed in all dialogs from which forms can be printed	
CAQ Form descriptions	• Displayed in master data, forms • Displayed in all dialogs from which forms can be printed	
CAQ Dynamic modification norm	• Display in dynamic modification norms • Inspection plans (WEP) • Characteristics (WEP) • Inspection orders (WEP)	
CAQ Designation of inspection severity definition	• Displayed in master data, inspection severity definition	

	• Inspection plans (WEP) • Characteristics (WEP) • Inspection orders (WEP)	
CAQ Designation of inspection severity	• Displayed in entries of inspection severity definitions • Inspection plans (WEP) • Characteristics (WEP) • Inspection orders (WEP)	
CAQ Designation of transitional definitions	• Displayed in master data, transitional definitions • Inspection plans (WEP) • Characteristics (WEP) • Inspection orders (WEP)	
CAQ Characteristic designation	• Displayed in master data catalog of characteristics • Inspection plan characteristics • Inspection order characteristics • PLP characteristics • EMU characteristics • Complaint details of characteristics	
CAQ Characteristic location	• Displayed in master data catalog of characteristics • Inspection plan characteristics • Inspection order characteristics • PLP characteristics • EMU characteristics • Complaint details of characteristics • Terminal	

CAQ Gage designation	• Displayed in gage master data, gage management • Characteristics • Terminal	
CAQ Designation of inspection station	• Displayed in characteristics	
CAQ Article designation	• Displayed in master data articles • Inspection plans • Inspection requirements • Complaint details	
CAQ Defect designation	• Displayed in master data defect catalogs	
CAQ Designation of measures	• Displayed in master data, measures • Evaluation of measures • Complaint header • Complaint details	
CAQ Measure text	• Master data of measures	
CAQ Document designation	• Master data characteristics • Inspection plan header • Inspection requirement header • Inspection plan characteristics • Inspection order characteristics • Test equipment management • Complaint header and details	
CAQ Document entries	•	
CAQ Documents	•	

CAQ Cost type designation	• Displayed in master data, cost types • Complaint header • Complaint details	
CAQ MDI channel designation	• Displayed in master data, MDI configuration	
CAQ Workflow Element designation	• Displayed in master data, workflow • Complaint header workflow • Complaint detail workflow	
CAQ Workflow Measure text	• Workflow element (master data, complaint detail, complaint header)	
CAQ Designation of analysis selection catalog	• Displayed in master data, analysis selection catalog • Displayed in characteristics	
CAQ Evaluation catalog, designation of the entry	• Supplier evaluation and • master data evaluation catalog	
CAQ Designation of evaluation groups	• Supplier evaluation and • master data evaluation catalog	
CAQ Designation of evaluation elements	• Displayed in evaluation catalogs -> entries	
CAQ Evaluation catalog number	• Displayed in evaluation catalogs	
CAQ Designation of evaluation classes	• Displayed in evaluation catalogs -> classes	
CAQ Designation of certificate characteristics	• Displayed in inspection plan --> certificates	
CAQ	• Displayed in master data	

Designation of distributor		
CAQ Designation of companies	• Displayed in master data, company • Inspection requirements • Test equipment management • When the responsible parties are assigned. • External persons	
CAQ Company's country of residence	• Displayed in master data, company catalog	
CAQ Designation of department	• Displayed in master data, department • When the responsible parties are assigned. • External persons	
CAQ Party in charge name 1	• Displayed in all dialogs where parties in charge may be selected	
CAQ Party in charge name 2	• Displayed in all dialogs where parties in charge may be selected	
CAQ Party in charge name 3	• Displayed in all dialogs where parties in charge may be selected	
CAQ Designation of units	• Currently not displayed •	
MOC Administration		
MDE Resource status types	• Displayed in the resource status type dialog (MOC)	
MDE Resource status texts	• Displayed in resource status texts dialog (MOC)	
MDE Production levels	• Configuration • The designation is displayed in the corresponding language	

SYS Enhanced object configuration	• Configuration • The designation is displayed in the corresponding language	
MDE Machine counter	• Configuration (MOC) • The designation is displayed in the corresponding language (MOC)	
PDV Event designation	• Configuration (MOC) • The designation is displayed in the corresponding language (MOC)	
CAQ QM catalog	• Configuration (console) • The designation is displayed in the corresponding language (CTAIP)	

Translation of database texts for MDBI

Initial database texts are translated by way of the “System Text Configurator” tool.

This tool makes it possible to translate a specified amount of database texts manually and in a semi-automated way using data from the HYDRA dictionary.

The tool is stored in the following directory on the HYDRA server:

UNIX: <HYDRADIR>/admtools/systemtextconfigurator

Windows: <HYDRA>\admtools\systemtextconfigurator

MpdvStc.jar

The documentation dealing with the tool can be found in the following directory:

UNIX: <HYDRADIR>/admtools/systemtextconfigurator/help

Windows: <HYDRA>\admtools\systemtextconfigurator\help

Before the STC tool is used, it has to be configured according to the documentation (e.g. DB-Connection).

Annex

- A Internal description of the HYD-MDBI function**
- B Initialization of new columns**
- C Further creation/checking of MDBI columns**
- D Disabling of MDBI languages**