

1 Reload Manager

Summary

HYDRA menu	System administration → Archiving → Reload manager
FEDRA menu	System administration → Archiving → Reload manager
Transaction code	arcrlid
Function authorization	arcrlid arcrlid.export arcrlid.import

Purpose

The customer is responsible for backing up data in a data archive and for restoring data. When data is backed up it is transferred from the long-term data area to the archive data area and, as a result, it is stored in a separate file system. The customer can start the backup process using the Reload Manager.

When data, which is filed in the archive data area, is restored, it is transferred back (copied) to the long-term data area. The customer has to do this and bears the responsibility.

To be able to evaluate restored data using standard evaluations/reports, the data has to be transferred back (copied) to the reload data area.

For this reason, the Reload Manager enables the following functions:

1. Moving of exported data into the customer archive (the customer archive path has to be defined within the HYDRA path settings).
2. Loading of exported data into the reload area for evaluations

Integration

The Reload Manager is a central function that is used by many components or functions.

Selection Criteria

The application provides the following selection criteria:

Module

Reference to the product group which archived data belongs to.

Object type

Object type of the archived data.



The selection options “module” and “object type” are mandatory fields.

Toolbar

Export

The “EXPORT” button allows for the entries selected in the Reload Manager to be exported to the customer directory (all data records can be selected using the context menu of the right mouse button). Once the function has been started, the input dialog that opens requires the customer archive path to be entered.

Import

The “IMPORT” button allows for the selected entries to be loaded into the reload area, in order for the data to be again available for HYDRA evaluations/reports. Once the function has been started, the data loading mode and an optional path are requested. By indicating the path, it is possible to specify another storage location for the files, provided that the archived files have not been moved to the customer-specific archive using the Reload Manager.

There are three different ways to deal with reload data after they have been reloaded to prevent the reload data set from increasing excessively (→ no slow evaluations/reports):

The following modes are distinguished:

- **Cyclic**
Data is loaded to the reload area in the “cyclic” mode. Loaded data is automatically removed from the corresponding reload tables, once the retention period specified within archive settings has expired.
Please compare the configuration entry HYD / RELOADMANAGER of the data management function. When demo settings are used, data is removed from the reload area after 14 days.

When data is imported, the HYD_REL_MANAGEMENT.DELETE_DATE field is calculated subject to the configuration and entered in the reload management table.

- **User-specific**
Data is loaded to the reload area in the “user-specific” mode. The loaded data is automatically removed from the corresponding reload area, once the time specified for the user within the user-specific settings has expired. Exception: In case several users loaded identical data into the reload area, the corresponding retention period is automatically set to the maximum date.
When data is imported, the HYD_REL_MANAGEMENT.DELETE_DATE field is computed subject to the configuration and entered in the reload management table.

- Manual

Data is loaded in the “manual” mode to the reload area. The customer is responsible for deleting data from corresponding reload tables. However, identical data cannot be loaded several times in the “manual” mode (data can be loaded in the “user-specific” mode though).

In order for data to be transferred to the reload data area, the HYDRA server must be able to access these files. Otherwise, loading is cancelled with an error message.