

1 Cost Center Posting

Summary

The additional module “cost center posting” allows for a cost center to be recorded in addition to the clock-in and clock-out times. The cost center is entered every time when it comes to a clock-in or an alternate clocking. If no cost center is entered the system posts the hours worked onto the employee’s master cost center.

Consequently, it can be requested how much time has been posted onto the individual cost centers over any period of time. Another report shows how much time an employee has spent on the different cost centers.

The times are divided by wage types, which makes it possible to calculate the amount with which the cost center is to be charged.

Definition of cost centers

Cost centers are defined in the [cost centers](#) application.

Collection of cost centers at the terminal

There are different possibilities to enter the cost center at the terminal:

By cost center badges

In this context, a cost center badge is read in at the terminal before the clock-in is performed. The corresponding cost center is displayed and entered along with the clock-in that follows. This cost center will be charged until the next clock-in (with or without another cost center card) or clock-out takes place.

By cost center buttons

With this option, one or several function keys of the terminal are assigned to a cost center. Before clocking-in, the user has to decide on which cost center the time is to be posted. In this case as well, this cost center will be charged until the next clocking follows.

By a cost center list

With this option, a function key of the terminal is assigned to the cost center list function. This function key has to be selected prior to clocking-in. After posting using the staff badge, a list opens that includes all cost centers that exist for the employee’s company. The employee may select a cost center from the list. After affirming this by clicking “OK”, the cost center is posted with the clocking. In this case as well, this cost center will be charged until the next clocking follows.

By terminal configuration

If a cost center is entered within the [terminal configuration](#), all clocking records performed at this terminal will be posted on to the entered cost center. This cost center can be overridden by a cost center entered at the terminal using the cost center badges, cost center buttons or cost center list.



In the [basic parameter settings of PZE](#), it is possible to automatically interpret several, successive clocking-ins as alternate clockings. In this context, the previous clocking-in is automatically completed with a clocking-out.

Only terminals of the type series CT-36x, CT-37x and CT-38x support cost center lists.

Print Cost Center Badges

The [cost centers](#) application describes how cost center badges are printed.



Cost center badges require card cases that are wider than those for staff badges. The corresponding perforated paper can also be purchased from MPDV.

Cost center badges can only be printed if the corresponding company and cost center do not include lower case letters. Upper case letters are allowed only.

Configuration of a Cost Center Button

Cost center buttons are configured in the terminal configuration in the “HR functions” tab:

The screenshot shows the 'HR functions' tab in a configuration window. The 'Parameters' section includes fields for 'Operation mode' (AST), 'Cyclic loading' (1:00:00 h), 'Relay time' (2 s), 'Return time' (5 s), 'Display duration of info' (8 s), and 'Plausibility check' (None). There are also checkboxes for 'Show date of latest evaluation' and 'Show recent clocking records'. The 'Texts for key setting' section includes fields for 'Key In' (In), 'Key Out' (Out), 'Key Break' (Break), 'Key Information' (Info), 'Message key', and 'Text for default status'. The 'Texts for absence reasons' section includes fields for 'Absence reason 1' (KST), 'Absence reason 2' (KST), 'Absence reason 3', 'Absence reason 4', and their corresponding text fields (Absence reason text 1-4).

By entering “KST”, the corresponding button is defined as cost center button. The cost center is defined within the corresponding text. The designation of this cost center may be entered behind the cost center, separated by a blank. If a comma is inserted between the cost center and its designation only the cost center designation will be displayed on the function key and when cost centers are posted.



Cost center keys are only supported by terminals of the types series CT-36x, CT-37x and CT-38x.

Configuration of a Cost Center List

The key for the cost center list is also configured within the terminal configuration in the “HR functions” tab:

The screenshot shows the 'Edit' window for Cost Center Posting. The 'General' tab is selected, displaying various parameters and text settings. The 'Parameters' section includes fields for Operation mode (AST), Cyclic loading (1:00:00 h), Relay time (2 s), Return time (5 s), Display duration of info (8 s), and checkboxes for 'Show date of latest evaluation' and 'Show recent clocking records'. The 'Texts for key setting' section contains input fields for Key In (In), Key Out (Out), Key Break (Break), Key Information (Info), Message key, and Text for default status. The 'Texts for absence reasons' section contains a table with four rows for absence reasons and their corresponding text labels.

Texts for absence reasons			
Absence reason 1		Absence reason text 1	
Absence reason 2		Absence reason text 2	
Absence reason 3		Absence reason text 3	
Absence reason 4	KSL	Absence reason text 4	Cost centers

The entry "KSL" defines the corresponding key for the cost center list. The key labeling is defined within the designation field.



Only terminals of the type series CT-36x, CT-37x and CT-38x support cost center lists.

Evaluations By Cost Centers

The [wage type statistics](#) dialog provides the “charged cost center” category.

A list showing the times incurred per cost center is displayed by grouping the “charged cost center” column, for example.

Wage type statistics

Main page Profile

Request data Cancel Print preview Print all Labor time maintenance Personnel scheduling Delete selected lines Save Help on operation Help on application Help on detail application

Selection

Person from to Company Area Cost center

Wage type statistics 1 Absence Statistics

Date 1/1/2011 to 2/28/2011

Maximum duration Minimum duration

Wage type statistics

Drag a column here to group by that column

Person	Wage type group	Wage type	Evaluation
Per... Name	Wage type group	Wage type designation	Weekday Date Duration
667 Smith, Christian	HOL Holiday	600 Publ.Hol.(absent)	Saturday 1/1/2011 8:00
667 Smith, Christian	HOL Holiday	600 Publ.Hol.(absent)	Thursday 1/6/2011 8:00
667 Smith, Christian	ILL Illness	400 Illness	Friday 1/7/2011 8:00
667 Smith, Christian	LEA Leave	450 Leave	Friday 1/14/2011 8:00
667 Smith, Christian	LEA Leave	450 Leave	Monday 1/17/2011 8:00
40256 Pernikova, Lisa	HOL Holiday	600 Publ.Hol.(absent)	Thursday 1/6/2011 8:00
40563 Green, Mary	HOL Holiday	600 Publ.Hol.(absent)	Thursday 1/6/2011 7:30
40563 Green, Mary	LEA Leave	450 Leave	Friday 1/28/2011 3:45
40789 Sheen, Edward	HOL Holiday	600 Publ.Hol.(absent)	Thursday 1/6/2011 7:30
40789 Sheen, Edward	LEA Leave	450 Leave	Monday 1/10/2011 7:30
40789 Sheen, Edward	LEA Leave	450 Leave	Tuesday 1/11/2011 7:30
40789 Sheen, Edward	LEA Leave	450 Leave	Wednesday 1/12/2011 7:30
40789 Sheen, Edward	LEA Leave	450 Leave	Thursday 1/13/2011 7:30
			77 610:30:00

Wage type statistics Bar chart

The cost center in the “person” category is the person’s master cost center.



When the wage types statistics function is configured, it has to be taken into account that the time to be evaluated (e.g. the attendance time) is completely represented by the selected wage types. In addition, it has to be ensured that no wage data is used, which includes the corresponding time twice or several times.