

1 Document Types

Overview

Menu	can be started by creating a new entry in the "document management" application
Transaction code	n/a
Function authorization	doctype

This configuration is used in order to create or change the document types available in the system. Document types are created for the entire system.

Utilization

There are different document types in order to classify document assignments and their properties.

In addition to just the classification, certain functions are also controlled using document types. Processing is controlled by indicating the link type within the document type.

Integration

Document types distinguish the different document assignments and specify the possibilities of document recording.

Toolbar

"General" tab



Add

Opens the dialog for adding a new document type.



Copy

Opens the dialog for copying a document type.



Edit

Opens the dialog for editing a document type.



Delete

Deletes a document type.

Selection criteria

The application provides the following selection criteria:

Document type

Selects the document type.

Description

This selection criterion refers to the description of the document type. Wildcard characters (placeholders) can be used.

Responsibility area

Selects the responsibility area.

Field Descriptions

Document type

"Self-explanatory" name for the document type

Description

Explanation of the document type. It is only used as commentary in HYDRA.

Responsibility area

The responsibility area which the document type is assigned to.



If displayed on the terminal screen (AIP), the responsibility area is not checked.

Link type

Indicates the link type. Four different link types are available:

(File, Filelink, URL and Text)

Path (only available with the link types FILE and/or FILELINK)

Path that can be configured in HYDRA in order to store files on the server (link type FILE) and/or to indicate the directory of the document files to be linked (link type FILELINK).

Sub-directory (only with link type FILE)

Specifies processing in the storage directory.

None

The file is stored in the directory according to the path configuration

System variable

The file is stored in a sub-directory of the directory mentioned in the configured path. There are two renaming options: YYYY-MM-DD and YYYY-MM-DD_HH-MM. With the first option a sub-directory is created by the day while transferring a file and the documents are stored there. If the second option is selected, documents are stored in minute by minute directories. If no such sub-directory is created, it will be issued automatically.

Customer-specific

Reserved for customizations with respect to file handling

File name (only with link type FILE)

Specifies processing with respect to the file name

None

The file is stored with its original file name in the server. It will not be renamed.

System variable

The file is renamed according to the selected renaming option. There are three renaming options: YYYY-MM-DD, YYYY-MM-DD_HH-MM and YYYY-MM-DD_HH-MM-SS. With the first option selected, the file name is changed to the current date while transferring the file. The second option sets the file name exactly to the minute and the third option sets it exactly to the second.

Customer-specific

Reserved for customizations with respect to file handling

Modified on

Time and date when the document type was changed at last.

Modified by

User who last changed and/or created the document type.

Link types

File

The selected file is transferred to the server and retrieved from there for display according to the configured document type and path.



If a document assignment of the link type "File" is deleted, the document file remains in the defined directory. The document file is not deleted.

Filelink

A file included in a defined directory (according to the path configured in the document type) is linked and retrieved from there for display. The document file is not transferred to the server when assigning the document.

URL

The link type "URL" allows indicating a URL link in order to access a file in the internet or intranet.

Text

The link type "text" enables text to be entered directly.