

1 Wage types

Overview

Menu	Master data → Labor time → Wage types
Transaction code	waty
Function authorization	waty

Wage types are different categories to group times with different information (e.g. night shift, overtime, etc.). We distinguish between basic wage types that are used for the payment of special working time and bonus wage. Usually, different types of absences are also specified as different wage types.

The screenshot displays the SAP 'Wage types' configuration window. The left pane shows a list of wage types with columns for 'Wage t...', 'Designation', and 'Authorization required'. The right pane shows the configuration for a specific wage type (01) with the designation 'LLE bonus/deduction'. The configuration includes fields for 'Wage type', 'Designation', 'Authorization required' (checked), 'Percentage' (100), 'Responsibility area', 'Payroll accounting' (with 'Upload wage type to payroll system' checked), 'Wage type', 'Control indicator', and 'Usage' (with 'Not defined' selected).

Field description tab "Wage type"

Wage type, name

Alpha numeric identification of the wage type and name.

Authorization required

This option is used to define a wage type with required authorization. If the option is not active, the system requires authorization somewhere else (e.g. in the payment day type).

Percentage

The percentage with which the wage type is compensated. Specifying a percentage only has an effect if the wage type is to be posted to an account. Otherwise, this is a comment field.



Entries with 0% are not posted.

Responsibility area

A user is only authorized to edit this wage type if he or she has authorization for the assigned area of responsibility.

Confirm wage type to payroll system

If an interface to Payroll Accounting exists, you can use this option to specify whether or not this wage type is transferred to the interface file.

Payroll wage type

You use the wage type to post information to the payroll department. This field is not processed in all interfaces.

Payroll control option

A field for customer specific processing.

Purpose

Specifies whether the wage type should be used to calculate planned working time, overtime or undertime. It is also possible not to specify anything. The wage types marked with Overtime are listed in the Overtime column of the time sheet. The same applies to the use of Undertime, but these times are displayed as negative.

Type

Specifies whether the wage type is a basic or a bonus wage type.

Field description tab "Settings"**Processing**

Note on how this wage type is used. This is a comment field and can be left empty.

Selection field

A field for customer specific processing.

Average Type

The field "Average type" is processed with the aid of interfaces to transfer "Monthly wage types" to the payroll systems LOGA and Abacus. You can find further information in the description of the interfaces.

Rounding of wage type

The fields "Interval" and "Limit" (both in the format hours:minutes) can be used for rounding the daily duration of a wage type. The interval forms the points in time used to round up or down. The limit specifies up to what point in time the system rounds down during the interval and when it rounds up. If no rounding to wage types is required, you do not need to make an entry.



Wage types are rounded after the "Additional allowances rule" and the "Wage type interaction" were processed.

Use wage type for comparison with BDE.

You can use the Comparison function to compare data in the order data entry for rounding in personnel time recording. This is done with the wage types that are marked here.

Delete wage type after comparison with BDE.

If this wage type is only a processing wage type for comparison and can be deleted after the comparison.

Field description Tab "Incentive wage"**Time type**

This field specifies the "Time wage, "Piecework" and "Overhead costs".

Labor time for incentive wage

This wage type is used to deduce the PZE labor time from the PZE wage type posting when you calculate the performance efficiency rate for piecework from ADE and PZE.

If the wage type is activated with this option, then the PZE labor time is always deduced using the PZE wage type posting no matter what person. If the wage type cannot be activated with this option, then you use the attendance time from the PZE as the labor time.

Incentive wages option

You only use this option if you calculate a formula-based incentive wage with a customized processing.

Labor time for group bonus

This field controls how PZE wage type postings are included in the calculation of the group bonus using formula-based incentive wages. This field is not relevant if you have a standard group bonus without formula-based incentive wage calculation.

Not included in the group bonus

PZE wage type postings for this wage type are not included as labor time in the group bonus.

Using cost center for posting

The cost center in the PZE wage type posting is interpreted as a premium group. In this case, the cost center for the PZE and the premium groups of LLE must be identical. Transfers to other premium groups can be achieved by manually assigning:

cost centers in the PZE clockings and postings

temporary cost centers

HR master data versions

cost center entries at the PZE terminal

cost center changes.

Using premier groups from the HR master data

With this option you assign the PZE wage type postings entered in the premium groups using the premium group of the HR master data. Persons can be transferred to other premium groups on a daily basis by creating HR master data versions.

Using group assignments

You use the function "Change of group" to assign people to the premium groups down to the exact minute. The assignment from the group changes is transferred to the PZE wage type postings for this wage type and then you can include the wage type posting for the group calculation. In order to do so, you separate the wage type postings if a group change takes place during the posting.

Quantity determination by

You use this option to control how the quantities for piecework are calculated when persons are posted in the ADE. This is relevant for wage type with the time type "Piecework".

Basic settings

[LLE basic settings](#) The system calculates the quantities for the time ticket, which includes scrap and yield from the primary quantities if the setting is made.

Wage type

You can use the matrix to set which quantity fields of the ADE posting are used to calculate the quantity for the time ticket.

Toolbar



Update accounts

[Update accounts](#) With "Update accounts" you specify which wage types are used to increase or decrease amounts for certain accounts.

**Additional allowances rule**

You use the option "Add. allowances rule" to post an additional bonuses if employees work on special days. [Additional allowances rule](#) Likewise, fixed special payments such as fare, lunch money or similar can be made.

**Wage types relations**

You can configure interactions between wage types [Wage type interactions](#) .