

# 1 Documentation of Initial Sample Test Word Report

## Usage

The initial sample report shows initial sampling data for the VDA 2.4 report production process and product release. In this context data from the XML files listed in the section dealing with data sources is used.

## Requirements

The initial sample report is created using the initialsample\_vda24\_results\_de.dotm template and the macro library hydramacrolibrary.dotm.

## Procedure

Reports are created using the InspectionRequirementExport application that is started by the button “output form” of the initial sample application.

## Data sources

XML data sources are structured hierarchically and by counters. There is an XML file with detailed information on this data record for each data record of the correspondingly higher-level XML file.

### 1. root-<Zähler1>\_ReqList.xml

Includes header data of the initial sample inspection request.

Zähler1 corresponds to the initial sample inspection requirement selected in MOC.

#### 1.1. root-<Zähler1>-<Zähler2>\_CharList\_Req.xml

Includes the characteristics from the higher-level initial sample inspection requirement and the characteristic specifications.

Zähler1 corresponds to the higher-level initial sample inspection requirement which the characteristics are assigned to.

Zähler2 corresponds to the set of characteristics. In the area of initial sample inspection requirements this is only one set and, as a result, Zähler2 is always 1.

#### 1.2. root-<Zähler1>-<Zähler2>-<Zähler3>\_QMSingleValue\_Req.xml

Includes the inspection results for the corresponding characteristic. Subject to the structure of XML files, Zähler2 is always 1.

## Structure

The initial sample inspection report consists of one cover sheet and x enclosures that include the corresponding inspection results.

The cover sheet shows data from **root-<Zähler1>\_ReqList.xml**. There is also an auxiliary tool evaluating data from **root-<Zähler1>-<Zähler2>\_CharList\_Req.xml**. Further details are described in the section dealing with “UserExits”.

Tables on the cover sheet only provide layout functions and are not linked with differing data sources.

An enclosure sheet is created for every inspection category for which characteristics exist in **root-<Zähler1>-<Zähler2>\_CharList\_Req.xml**. There is only one page that is copied in the template.

This enclosure template also shows data from **root-<Zähler1>\_ReqList.xml** and **root-<Zähler1>-<Zähler2>\_CharList\_Req.xml**. The **Results** table includes characteristics and is linked with **root-<Zähler1>-<Zähler2>\_CharList\_Req.xml** as data source.

In the columns “actual values” “specification met” and “comment” the cells are merged and include a sub-table with inspection results.

**Root-<Zähler1>-1-<Zähler2>\_QMSingleValue\_Req.xml** is linked as data source for this table.

| Ref No.:                                                                                                                                  | Requirements                         | ACTUAL values                                               | Specification fulfilled             |                          | Comment                         |
|-------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------|-------------------------------------------------------------|-------------------------------------|--------------------------|---------------------------------|
|                                                                                                                                           | Specifications                       | Supplier                                                    | yes                                 | no                       |                                 |
| #LINK: inspectionplancharacteristic.stic.op<br>#LINK: inspectionplancharacteristic.stic.op<br>#LINK: inspectionplancharacteristic.stic.op | #LINK: qmcharacteristic.designation  | #LINK: qmsinglevalue.measured_value.value#FORMAT: DECPLACES | <input checked="" type="checkbox"/> | <input type="checkbox"/> | #LINK: qmsinglevalue.commentary |
|                                                                                                                                           | #LINK: qmcharacteristic.target_value |                                                             |                                     |                          |                                 |
|                                                                                                                                           | #LINK: unit.id                       |                                                             |                                     |                          |                                 |
|                                                                                                                                           | #LINK: LIMITS_SPECIAL                |                                                             |                                     |                          |                                 |

Subordinate table



Changes to columns of existing tables, table names or adding of new tables have to be taken into account in UserExits with respect to the position IDs that are used there.

## Special features

The document is write-protected when macro processing ends so that only content controls can be edited.

Only the enclosures, not the cover sheet are taken into account for page numbering.

The respective page number is reduced by 1 for the cover sheet which, as a result, has page number 0.

This has to be taken into account for printing specific page numbers.

## UserExits in use

The following UserExits are used:

### 1. UeLinkMasterCtrlToXmlBefore

Global variables and functions are defined.

The cover sheet has an auxiliary control element including the special formatting **FORMAT: SPECIALEMU** that is queried in this UE. If this option is set an array including all inspection categories from **root-<Zähler1>-<Zähler2>\_CharList\_Req.xml** is created, whereas every category is only transferred once, regardless of its occurrence.

The checkboxes for the corresponding enclosures on the cover sheet are set accordingly.

## 2. UeFillTableFromXmlAfter

In the **Results** table the first column **Ref-Nr.:** is sorted numerically.

## 3. UeLinkTableCtrlToXmlNotFound

Using a link to non-existing data element nodes **LIMITS\_SPECIAL** absolute tolerance limits from **root-<Zähler1>-<Zähler2>\_CharList\_Req.xml** are converted into relative tolerance limits. Special cases such as identical distances of the upper and lower tolerance to the target value are differentiated in this context. If invalid values are indicated **ERROR** will be displayed instead of the limit value.

| Ref No.:                                                                               | Requirements                                                                              | ACTUAL values                                                   |  | Specification fulfilled             |                          | Comment                         |
|----------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------|-----------------------------------------------------------------|--|-------------------------------------|--------------------------|---------------------------------|
|                                                                                        | Specifications                                                                            | Supplier                                                        |  | yes                                 | no                       |                                 |
| #LINK: inspectionplancharacteristicop<br>#LINK: inspectionplancharacteristicassignment | #LINK: qmcharacteristic.designation                                                       | #LINK: qmsinglevalue.measured_value.value                       |  | <input checked="" type="checkbox"/> | <input type="checkbox"/> | #LINK: qmsinglevalue.commentary |
|                                                                                        | #LINK: qmcharacteristic.target_value<br>#LINK: ToleranceLimits.d<br>#LINK: LIMITS_SPECIAL | #LINK: qmsinglevalue.measured_value.value<br>#FORMAT: DECPLACES |  |                                     |                          |                                 |

link to non-existing data element node as UserExit entry point

## 4. UeFillRowFromXmlAfter

At first texts are defined that indicate inspection results that are not valid in **root-<Zähler1>-<Zähler2>\_CharList\_Req.xml**. Default values are “fail” and “pass”. If other texts are used it has to be adjusted accordingly. Lower-case letters are to be used.

The corresponding checkbox for “specification met” is now set for the **Values** table.

## 5. UeOutputReportBefore

For performance reasons, the template is once filled with all inspection results and then copied for every inspection category.

The corresponding checkbox of the inspection category is set and all inspection results that are not assigned to the corresponding inspection category are deleted.

Furthermore, all auxiliary tools included in this UserExit are either deleted or the included text is deleted.

Finally, the focus is set on the first content control that has not been filled out automatically and the document is write-protected. To do so, the password **MPDV** is set.