

Manual

Escalation Messages of PZW PZW-ESK 8.2

Version 1.0.15126

Last changed on: 19.06.2020

Copyright

©Copyright 2020 All rights reserved.

SAP® and R/3® are registered trademarks of SAP AG.

WINDOWS® is a registered trademark of Microsoft Corporation.

MPDV® and HYDRA® are registered trademarks of MPDV Mikrolab GmbH.

ORACLE® is a registered trademark of ORACLE Corporation, California, USA.

Copying and distribution of this documentation or any part thereof, for any purpose or in any form, is prohibited without prior written permission from MPDV Mikrolab GmbH.

The information contained in this documentation is subject to change without prior notice.

Contents

1	PZW Escalation Messages – Overview	4
2	Escalations available for Personnel Time Management	5
2.1	Clocking failure with person (PNR.CLOCKING_FAILURE)	5
2.2	Absence created (FZ.INSERTED)	7
2.3	Absence changed (FZ.UPDATED)	8
2.4	Absence deleted (FZ.DELETED)	9
2.5	A person joining the company (PNR.JOINING)	10
2.6	A person leaving the company (PNR.LEAVING)	12
2.7	A person's birthday (PNR.BIRTHDAY)	14
2.8	A person's company anniversary (PNR.JUBILEE)	16
2.9	Unplanned absence (PNR.UNPLANNED_ABSENCE)	18
2.10	End of continued pay (PNR.END_OF_CONTINUED_PAY)	20

1 PZW Escalation Messages – Overview

Purpose

Application Service to generate events or to send messages in the HYDRA Personnel Time Management (PZW).

Implementation notes

You use the function package for the following purposes:

- You want to be informed when absences are created, modified or deleted.
- You want to be informed in time when an employee joins or leaves the company or in case of a birthday or company anniversary of an employee.
- You want to be informed before the period of continued pay ends when an employee receives continued pay.
- You want to be informed when an employee is absent (unplanned).

Integration

If an escalation must be triggered in case of an unplanned absent employee, you must first store the planned working time of the employee in the Personnel Time Management (function package: *labor time assessment*).

Features

- Escalations of the Personnel Time Management
 - Employees that arrive too late or are absent unplanned
 - Information on planned absences
 - Reminders when employees are joining or leaving the company, when there are birthdays and company anniversaries of employees
 - Notification before the period of continued pay ends

2 Escalations available for Personnel Time Management

This document describes the escalations available in PZW. If an escalation is to be enabled, a respective [configuration](#) has to be created for this escalation.

2.1 Clocking failure with person (PNR.CLOCKING_FAILURE)

The escalation *PNR.CLOCKING_FAILURE* will be generated if the error "wrong status sequence" occurs during work day evaluation. This escalation can, for example, be used to inform the supervisor by e-mail or the employee at the terminal.

With the [configuration of escalations](#) the recipient type *Automatic* causes the message to be sent to the person for whom the escalation was created.

The text for the notification can be configured in the "message" tab:

The screenshot shows a software window titled "Insert" with a standard Windows-style title bar (minimize, maximize, close buttons). Inside the window, there are four tabs: "Event", "Message", "Notification", and "Condition". The "Message" tab is currently selected. On the left side of the "Message" tab, there are labels for "Subject" and "Text". The "Subject" field contains the text "Clocking failure occurred". The "Text" field is a large text area containing the message body: "A clocking failure occurred at %STMP.ABREDATA date dd.mm.yyyy%.". Below the text area, there are two dropdown menus labeled "Available placeholders" and "System variables", both of which are currently empty. The window also features a small icon with a green checkmark and a red X in the top-left corner of the main content area.

The "notification" tab can be used to define whether the message is to be sent by e-mail or displayed on the PZE terminal.

If notifications are to be performed via the terminal, the messages and clocking authorizations are loaded cyclically onto the PZE terminals. Consequently, the messages are available on the terminal (provided that the terminal is online) at the latest after the duration "cyclic loading" that is set in the [terminal configuration](#) within the "HR functions" tab. In case a message was displayed, it is marked as being read and is no longer transferred to the terminal with the next cyclic loading interval. However, the message can be displayed several times within one cyclic loading time.

By correcting the clocking failure and performing the work-day evaluation, the escalation is finished and the message is deleted for the display, provided it has not yet been shown. The message will no longer be available and displayed on the terminal at the latest after a cyclic loading time.

Please note:

Messages can only be displayed on terminals of the type CT-38x and CT-37x.

The following placeholders are available for the creation of the message or to define the conditions:

Event	Identifiers	Description
PNR.CLOCKING_FAILURE	PNR.PNR	Personnel number
	STMP.ABREDAT	Evaluation date
	PNR.NAME	The person's name
	PNR.PNAME	The person's surname
	PNR.PVORNAME	The person's first name
	PNR.FIR	Company pertaining to the personnel number
	PNR.BER	The person's area
	PNR.KST	The person's cost center
	PNR.ABT	The person's department
	PNR.PKREIS	The person's employee subgroup

2.2 Absence created (FZ.INSERTED)

The escalation *FZ.INSERTED* is generated if an absence is created. This escalation can, for example, be used to inform the supervisor by e-mail.

The following placeholders are available for the creation of the message or to define the conditions:

Event	Identifiers	Description
FZ.INSERTED	FZ.FIR	Company
	FZ.PNR	Personnel number
	FZ.NAME:PNR	Name
	FZ.PNAME	Last name
	FZ.PVORNAME	First name
	PNR.BER	Area
	PNR.KST	Cost center
	PNR.ABT	Department
	PNR.PKREIS	Employee subgroup
	PNR.TAETIGKEIT	The person's activity

	PNR.BESCHVERH	Employment relationship
	PNR.TEL:FIR	Phone, company
	PNR.EMAIL:FIR	E-Mail, company
	FZ.ENTLTMOD	Absence payment
	FZ.BEZK:ENTLTMOD	Abbreviation of the absence
	FZ.BEZL:ENTLTMOD	Absence designation
	FZ.KAT	Absence category
	FZ.DAT:APPLY	Date of application
	FZ.ZEI:APPLY	Time of application
	FZ.DATB	Start date
	FZ.DATE	End date
	FZ.BEZL	Comment
	FZ.VERWEIS	Unique record number

2.3 Absence changed (FZ.UPDATED)

The escalation *FZ.UPDATED* is generated if an absence is modified. This escalation can be used, for example, to inform the supervisor by e-mail.



The escalation *FZ.UPDATED* is only triggered if the period or absence payment is changed by modifying a person's absence.

The following placeholders are available for the creation of the message or to define the conditions:

Event	Identifiers	Description
FZ.UPDATED	FZ.FIR	Company
	FZ.PNR	Personnel number
	FZ.NAME:PNR	Name
	FZ.PNAME	Last name
	FZ.PVORNAME	First name
	PNR.BER	Area
	PNR.KST	Cost center
	PNR.ABT	Department
	PNR.PKREIS	Employee subgroup
	PNR.TAETIGKEIT	The person's activity
	PNR.BESCHVERH	Employment relationship
	PNR.TEL:FIR	Phone, company
	PNR.EMAIL:FIR	E-Mail, company
	FZ.ENTLTMOD	Absence payment
	FZ.BEZK:ENTLTMOD	Abbreviation of the absence
	FZ.BEZL:ENTLTMOD	Absence designation
	FZ.KAT	Absence category
	FZ.DAT:APPLY	Date of application
	FZ.ZEI:APPLY	Time of application
	FZ.DATB	Start date
	FZ.DATE	End date
	FZ.BEZL	Comment
	FZ.VERWEIS	Unique record number

	FZ.ENTLTMODV	Previous absence payment
	FZ.BEZH:ENTLTMODV	Previous abbreviation of the absence
	FZ.BEZH:ENTLTMODV	Previous absence designation
	FZ.KATV	Previous absence category
	FZ.DATBV	Previous start date
	FZ.DATEV	Previous end date

2.4 Absence deleted (FZ.DELETED)


The escalation *FZ.DELETED* is generated if an absence is deleted. This escalation can be used, for example, to inform the supervisor by e-mail.

The following placeholders are available for the creation of the message or to define the conditions:

Event	Identifiers	Description
FZ.DELETED	FZ.FIR	Company
	FZ.PNR	Personnel number
	FZ.NAME:PNR	Name
	FZ.PNAME	Last name
	FZ.PVORNAME	First name
	PNR.BER	Area
	PNR.KST	Cost center
	PNR.ABT	Department
	PNR.PKREIS	Employee subgroup
	PNR.TAETIGKEIT	The person's activity
	PNR.BESCHVERH	Employment relationship
	PNR.TEL:FIR	Phone, company
	PNR.EMAIL:FIR	E-Mail, company
	FZ.ENTLTMOD	Absence payment
	FZ.BEZH:ENTLTMOD	Abbreviation of the absence
	FZ.BEZH:ENTLTMOD	Absence designation
	FZ.KAT	Absence category
	FZ.DAT:APPLY	Date of application
	FZ.ZEI:APPLY	Time of application
	FZ.DATB	Start date
	FZ.DATE	End date
	FZ.BEZH	Comment
	FZ.VERWEIS	Unique record number

2.5 A person joining the company (PNR.JOINING)

The escalation *PNR.JOINING* is generated daily up to 50 days prior to the person joining the company. The variable *PNR.DAUER_EINTRITT* and a condition define how many days prior to the person joining the company the message is to be displayed:



The screenshot shows a software interface for configuring escalation messages. The window is titled 'Main page' and has a toolbar with a green checkmark, a red X, and a dropdown arrow. Below the toolbar are four tabs: 'Event', 'Message', 'Notification', and 'Condition'. The 'Condition' tab is selected, and it contains a large text area with the condition `PNR.DAUER_EINTRITT == 14`. Below the text area are two empty input fields labeled 'Variables' and 'System variables'.

In this example, the message about a person joining the company is generated 14 days prior to the date of joining.


The following placeholders are available for the creation of the message or to define the conditions:

Event	Identifiers	Description
PNR.JOINING	PNR.FIR	Company
	PNR.PNR	Personnel number
	PNR.NAME:PNR	Name

	PNR.PNAME	Last name
	PNR.PVORNAME	First name
	PNR.BER	Area
	PNR.KST	Cost center
	PNR.ABT	Department
	PNR.PKREIS	Employee subgroup
	PNR.TAETIGKEIT	The person's activity
	PNR.BESCHVERH	Employment relationship
	PNR.TEL:FIR	Phone, company
	PNR.EMAIL:FIR	E-Mail, company
	PNR.EINTRITT	Date of joining
	PNR.DAUER_EINTRITT	Number of days until the person joining the company
	PNR.VGS:PNR	The supervisor's personnel number
	PNR.VGS:FIR	The supervisor's company

2.6 A person leaving the company (PNR.LEAVING)

The escalation *PNR.LEAVING* is generated on a daily basis up to 50 days prior to the person leaving the company. The variable *PNR.DAUER_AUSTRITT* can be set in the condition wizard and defines how many days prior to the person leaving the company the message is to be displayed:



The screenshot shows a software window titled 'Insert'. It has a 'Main page' tab and a 'Condition' section. The 'Condition' section contains the text 'PNR.DAUER_AUSTRITT == 30'. Below this are two empty fields labeled 'Variables' and 'System variables'.

In this example the message about a person leaving the company is generated 30 days prior to the date of leaving.


The following placeholders are available for the creation of the message or to define the conditions:

Event	Identifiers	Description
PNR.LEAVING	PNR.FIR	Company
	PNR.PNR	Personnel number
	PNR.NAME:PNR	Name

	PNR.PNAME	Last name
	PNR.PVORNAME	First name
	PNR.BER	Area
	PNR.KST	Cost center
	PNR.ABT	Department
	PNR.PKREIS	Employee subgroup
	PNR.TAETIGKEIT	The person's activity
	PNR.BESCHVERH	Employment relationship
	PNR.TEL:FIR	Phone, company
	PNR.EMAIL:FIR	E-Mail, company
	PNR.AUSTRITT	Date of leaving
	PNR.DAUER_AUSTRITT	Number of days until the person leaving the company
	PNR.VGS:PNR	The supervisor's personnel number
	PNR.VGS:FIR	The supervisor's company

2.7 A person's birthday (PNR.BIRTHDAY)

The escalation *PNR.BIRTHDAY* is generated on a daily basis up to 50 days prior to a person's birthday. The variable *PNR.DAUER_GEBDAT* can be set in the condition wizard and defines how many days prior to the birthday the message is to be displayed:



The screenshot shows a software window titled 'Main page' with a tabbed interface. The 'Condition' tab is active, displaying the text: `PNR.DAUER_GEBDAT == 30 and PNR.GEBDAT:RUND >= 5`. Below this text are two empty input fields labeled 'Variables' and 'System variables'.

In this example, the message is generated on the person's birthday if it is a "big" birthday that can be divided by 5 or 10.


The following placeholders are available for the creation of the message or to define the conditions:

Event	Identifiers	Description
PNR.BIRTHDAY	PNR.FIR	Company
	PNR.PNR	Personnel number
	PNR.NAME:PNR	Name

	PNR.PNAME	Last name
	PNR.PVORNAME	First name
	PNR.BER	Area
	PNR.KST	Cost center
	PNR.ABT	Department
	PNR.PKREIS	Employee subgroup
	PNR.TAETIGKEIT	The person's activity
	PNR.BESCHVERH	Employment relationship
	PNR.TEL:FIR	Phone, company
	PNR.EMAIL:FIR	E-Mail, company
	PNR.GEBTG	Date of the next birthday
	PNR.GEBDAT	Date of birth
	PNR.DAUER_GEBDAT	Number of days until the birthday
	PNR.GEBDAT:RUND	Milestone birthdays: 10 = birthday can be divided by 10 5 = birthday can be divided by 5 1 = no "big" birthday
	PNR.ALTER	Age in years
	PNR.VGS:PNR	The supervisor's personnel number
	PNR.VGS:FIR	The supervisor's company

2.8 A person's company anniversary (PNR.JUBILEE)

The escalation PNR.JUBILEE is generated on a daily basis up to 50 days prior to the person's company anniversary. The variable PNR.DAUER_JUBIDAT can be set in the condition wizard and defines how many days prior to the anniversary the message is to be displayed:



The screenshot shows a software window titled 'Insert'. It has a toolbar with a green checkmark, a red X, and a dropdown arrow. Below the toolbar is a 'Main page' section with four tabs: 'Event', 'Message', 'Notification', and 'Condition'. The 'Condition' tab is active, displaying a text area with the condition: `PNR.DAUER_JUBIDAT == 14 and PNR.JUBIDAT:RUND == 10`. To the left of the text area is a label 'Condition'. Below the text area are two dropdown menus labeled 'Variables' and 'System variables'.

In this example, the message is generated 14 days prior to the person's company anniversary if it is a "milestone" anniversary that can be divided by 10.


The following placeholders are available for the creation of the message or to define the conditions:

Event	Identifiers	Description
PNR.JUBILEE	PNR.FIR	Company
	PNR.PNR	Personnel number
	PNR.NAME:PNR	Name

	PNR.PNAME	Last name
	PNR.PVORNAME	First name
	PNR.BER	Area
	PNR.KST	Cost center
	PNR.ABT	Department
	PNR.PKREIS	Employee subgroup
	PNR.TAETIGKEIT	The person's activity
	PNR.BESCHVERH	Employment relationship
	PNR.TEL:FIR	Phone, company
	PNR.EMAIL:FIR	E-Mail, company
	PNR.EINTRITT	Date of joining
	PNR.JUBIDAT	Date of the company anniversary
	PNR.DAUER_JUBIDAT	Number of days until the anniversary
	PNR.JUBIDAT:RUND	Milestone company anniversary: 10 = anniversary can be divided by 10 5 = anniversary can be divided by 5 1 = no "big" anniversary
	PNR.JUBI	Company anniversary in years
	PNR.VGS:PNR	The supervisor's personnel number
	PNR.VGS:FIR	The supervisor's company

2.9 Unplanned absence (PNR.UNPLANNED_ABSENCE)

The escalation *PNR.UNPLANNED_ABSENCE* is processed in cyclic intervals (e.g. every 15 minutes). The variable *PNR.ABWDAU* can be set in the condition wizard and defines how long the person has at least to be absent (unplanned) before the escalation can be triggered:



The screenshot shows a software window titled 'Main page' with a toolbar at the top containing a green checkmark, a red X, and a dropdown arrow. Below the toolbar are four tabs: 'Event', 'Message', 'Notification', and 'Condition'. The 'Condition' tab is active, displaying a large text area with the condition 'PNR.ABWDAU >= 1800'. To the left of this text area is a label 'Condition'. Below the text area are two empty input fields: 'Variables' and 'System variables'.

In this example, the escalation is only triggered if the employee is absent (unplanned) for at least 30 minutes (1800 seconds).


The following placeholders are available for the creation of the message or to define the conditions:

Event	Identifiers	Description
PNR.UNPLANNED_ABSENCE	PNR.FIR	Company
	PNR.PNR	Personnel number
	PNR.NAME:PNR	Name

	PNR.PNAME	Last name
	PNR.PVORNAME	First name
	PNR.BER	Area
	PNR.KST	Cost center
	PNR.ABT	Department
	PNR.PKREIS	Employee subgroup
	PNR.TAETIGKEIT	The person's activity
	PNR.BESCHVERH	Employment relationship
	PNR.TEL:FIR	Phone, company
	PNR.EMAIL:FIR	E-Mail, company
	PNR.ABWDAT	Start date of unplanned absence
	PNR.ABWZEI	Start time of unplanned absence
	PNR.ABWDAU	Previous duration of the unplanned absence
	PNR.ANW	J = Person was present before N = Person was not present before
	PNR.VGS:PNR	The supervisor's personnel number
	PNR.VGS:FIR	The supervisor's company

2.10 End of continued pay (PNR.END_OF_CONTINUED_PAY)

The escalation *PNR.END_OF_CONTINUED_PAY* is generated on a daily basis up to 50 days prior to the end of a person's continued pay. The variable *PNR.DAUER_OLFZ* can be set in the condition wizard and defines how many days prior to the end of continued pay the message is to be displayed:



The screenshot shows a software window titled "Insert" with a "Main page" tab. Inside, there are four tabs: "Event", "Message", "Notification", and "Condition". The "Condition" tab is active, displaying a text area with the condition `PNR.DAUER_OLFZ <= 14`. Below this text area are two empty input fields labeled "Variables" and "System variables".

In this example, a message is generated for the relevant person 14 days prior to the end of continued pay. The operator "`<=`" (less than or equal to) causes the message to be generated even if the end of continued pay is reached in less than 14 days, e.g. due to short-term planning. But this also results in the escalation to be generated once more the next day even if the escalation is finished prior to the end of continued pay. Escalation Management creates this escalation on a daily basis, provided it is not already available for the person and the end date of continued pay. With the operator "`=`", the escalation is not triggered several times and is also omitted if the end of continued pay lies less than 14 days in the future, e.g. due to the assignment of a previous illness.

The following placeholders are available for the creation of the message or to define the conditions:

Event	Identifiers	Description
PNR.END_OF_CONTINUED_PAY	PNR.FIR	Company
	PNR.PNR	Personnel number
	PNR.NAME:PNR	Name
	PNR.PNAME	Last name
	PNR.PVORNAME	First name
	PNR.BER	Area
	PNR.KST	Cost center
	PNR.ABT	Department
	PNR.PKREIS	Employee subgroup
	PNR.TAETIGKEIT	The person's activity
	PNR.BESCHVERH	Employment relationship
	PNR.TEL:FIR	Phone, company
	PNR.EMAIL:FIR	E-Mail, company
	PNR.DATE_LFZ	End of continued pay
	PNR.DATB_OLFZ	First day without continued pay
	PNR.DAUER_OLFZ	Number of days until continued pay ends
	PNR.VGS:PNR	The supervisor's personnel number
	PNR.VGS:FIR	The supervisor's company