



SUREN NETWORK
PLAY WITH TECHNOLOGIES

SSH - TELNET




```

ROUTER#
ROUTER#
ROUTER#
ROUTER#show ip interface brief

```

Interface	IP-Address	OK?	Method	Status	Prot
Ethernet0/0	unassigned	YES	TFTP	up	up
Ethernet0/1	unassigned	YES	TFTP	down	down
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

```

ROUTER#
ROUTER#config t
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#interface ethernet 0/0
ROUTER(config-if)#ip address 50.0.0.1 255.0.0.0
ROUTER(config-if)#no shutdown
ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#
*Aug 18 15:51:00.806: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#
ROUTER#

```

```

ROUTER#show ip interface brief

```

Interface	IP-Address	OK?	Method	Status	Prot
Ethernet0/0	50.0.0.1	YES	manual	up	up
Ethernet0/1	unassigned	YES	TFTP	down	down
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

I

```

ROUTER#
ROUTER#
ROUTER#config t
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#
ROUTER(config)#user name jaasir password 123
^
% Invalid input detected at '^' marker

```



```
ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#
*Aug 18 15:51:00.806: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#
ROUTER#
ROUTER#show ip interface brief

```

Interface	IP-Address	OK?	Method	Status	Prot
Ethernet0/0	50.0.0.1	YES	manual	up	up
Ethernet0/1	unassigned	YES	TFTP	down	down
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

```

ROUTER#
ROUTER#
ROUTER#config t
Enter configuration commands, one per line. End with CRTL/Z.
ROUTER(config)#
ROUTER(config)#user name jaasir password 123
^
% Invalid input detected at '^' marker.

ROUTER(config)#username jaasir password 123
ROUTER(config)#
ROUTER(config)#line console 0
ROUTER(config-line)#password 123
ROUTER(config-line)#
ROUTER(config-line)#login local
ROUTER(config-line)#
ROUTER(config-line)#exit
ROUTER(config)#
ROUTER(config)#exit
ROUTER#
*Aug 18 15:57:35.085: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#exit
```

I

ROUTER con0 is now available

Press RETURN to get started.

User Access Verification

Username: jaasir

Password:

ROUTER>

ROUTER>

ROUTER>

ROUTER>en

Password:

ROUTER#

ROUTER#

ROUTER#config t

Enter configuration commands, one per line. End with CNTL/Z.

ROUTER(config)#

ROUTER(config)#

ROUTER(config)#

ROUTER(config)#line vty 0 4

ROUTER(config-line)#transport input telnet

ROUTER(config-line)#login local

ROUTER(config-line)#exit

ROUTER(config)#

ROUTER(config)#

ROUTER(config)#

I



