

SlyBroadcast Connection Guide

How to switch on ringless voicemail so your drops actually deliver.

Three steps. About ten minutes of your time, then a short wait.

Read this first. Saving your SlyBroadcast email and password in your dashboard is only half of it. SlyBroadcast also has to turn on **API access** for your account. Until they do, every drop you send fails on their end. Your dashboard used to say "Sent" anyway - that was our fault and it is fixed, so you will now see the real error instead. Work through the three steps below and your drops will start landing.

Step 1 — Turn on API access inside SlyBroadcast

1 Do this on slybroadcast.com

- Log in at slybroadcast.com
- Click the **round account icon in the very top right** corner
- Choose **Integrations**
- Find the tile called **Slybroadcast API Access** and switch it **ON**
- When it is correct it reads "**API Enabled**"

If you cannot find Integrations, it is under the account icon, not the main menu. It is easy to walk straight past.

Step 2 — Send SlyBroadcast the request email

2 They must approve it on their side

- Open your business email webmail
- Go to the **Templates** folder, under your Inbox
- Open the ready-made email addressed to SlyBroadcast
- Click the **three-dot menu** and choose **Edit as new**
- Make sure your SlyBroadcast account email is in the body, then **Send**

SlyBroadcast usually enables API access within about 48 hours. Nothing you do on our side speeds that up, so send it as early in the day as you can.

Step 3 — Save your details in the dashboard

3 On usforeclosureleads.com

- Go to **My Account** → **Outreach Integrations**
- Enter your **SlyBroadcast account email and password** — the same ones you log into slybroadcast.com with
- Save
- Record a voice sample of about 30 seconds in **My AI Avatar / Ringless Drips** so your drops go out in your own voice

A common mix-up worth avoiding. SlyBroadcast uses only an **email and password**. It does not use an API Key or a Device ID. Those two belong to **TextBee**, which is texting, a completely separate tool. If you are being asked for an API Key, you are on the texting setup, not this one.

Do not want to do the technical part? Reply to our support email with your SlyBroadcast account email and password and we will enable the API and finish the connection for you. Plenty of agents choose this. It is not a problem.

How to tell it worked

Send one voice drop to a single lead. Then look at that lead:

- If it delivered, the lead shows the drop as sent and stays that way.

- If it failed, the lead now shows the actual error text. If it still says *"API access not allowed"*, SlyBroadcast has not finished approving you yet — wait out the 48 hours and try again.

Any drops that failed before are not lost. They have been released, so you can simply send them again once your account is approved.

Foreclosure Recovery Inc. — Any questions, reply to the email this guide came attached to and we will pick it up. Support runs 9:00 AM to 5:00 PM Pacific, seven days a week.