

EXPERIMENT 2

Design and configure the Switch network using cisco packet tracer


AIM :

To design and configure a network using a switch and five PCs in Cisco Packet Tracer with Class A IP addressing.


PROCEDURE :

1. Place a Switch-PT and five PCs (PC0–PC4) in Cisco Packet Tracer.
2. Connect each PC to the switch using Copper Straight-Through cables.
3. If required, power off the switch and install PT-SWITCH-NM-1CFE modules, then power it on.
4. Assign the following Class A IP addresses to the PCs:
 - PC0 – 10.1.1.1
 - PC1 – 10.1.1.2
 - PC2 – 10.1.1.3
 - PC3 – 10.1.1.4
 - PC4 – 10.1.1.5
5. Set the Subnet Mask for all PCs to 255.0.0.0.

BLOCK DIAGRAM :



OUTPUT :



```
Packet Tracer SERVER Command Line 1.0
SERVER>ipconfig

FastEthernet0 Connection: (default port)

    Link-local IPv6 Address.....: FE80::250:FFF:FE95:D0EE
    IP Address.....: 10.0.0.3
    Subnet Mask.....: 255.0.0.0
    Default Gateway.....: 0.0.0.0

SERVER>ping
Packet Tracer PC Ping

Usage: ping [-n count | -v TOS | -t ] target

SERVER>ping 10.0.0.4

Pinging 10.0.0.4 with 32 bytes of data:

Reply from 10.0.0.4: bytes=32 time=94ms TTL=128
Reply from 10.0.0.4: bytes=32 time=0ms TTL=128
Reply from 10.0.0.4: bytes=32 time=0ms TTL=128
Reply from 10.0.0.4: bytes=32 time=0ms TTL=128

Ping statistics for 10.0.0.4:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 94ms, Average = 23ms

SERVER>
```

RESULT :

The network was successfully configured, and all PCs communicated with each other through the switch.