ᐊᓂᔑᓂᓂᐅᐃᐤ - **Severn Ojibwa Keyboard** (Western-finals, left w-dot)

Unshifted

Consonant Key(s)		Vowel Key(s)						
		e	i	o	a	ii	oo	aa
		▽	△	▷	◁	Ȧ	Ḋ	◁̇
b / p	'	V	Λ	>	<	Λ̇	>̇	<̇
bw / pw		·V	·Λ	·>	·<	·Λ̇	·>̇	·<̇
d / t	'	U	∩	⊃	C	∩̇	⊃̇	Ċ
dw / tw		·U	·∩	·⊃	·C	·∩̇	·⊃̇	·Ċ
g / k	`	ᑫ	ᑭ	ᑯ	ᑲ	ᑭ̇	ᑯ̇	ᑲ̇
gw / kw		·ᑫ	·ᑭ	·ᑯ	·ᑲ	·ᑭ̇	·ᑯ̇	·ᑲ̇
j	¯	ᒉ	ᒋ	ᒍ	ᒐ	ᒋ̇	ᒍ̇	ᒐ̇
jw		·ᒉ	·ᒋ	·ᒍ	·ᒐ	·ᒋ̇	·ᒍ̇	·ᒐ̇
m	ᶜ	ᒣ	ᒥ	ᒧ	ᒪ	ᒥ̇	ᒧ̇	ᒪ̇
mw		·ᒣ	·ᒥ	·ᒧ	·ᒪ	·ᒥ̇	·ᒧ̇	·ᒪ̇
n	ᓄ	ᓀ	ᓂ	ᓄ	ᓇ	ᓂ̇	ᓄ̇	ᓇ̇
nw		·ᓀ			·ᓇ			·ᓇ̇
l		Ჽ▽	Ჽ△	Ჽ▷	Ჽ◁	ᲽȦ	ᲽḊ	Ლ◁̇
r		᠈▽	᠈△	᠈▷	᠈◁	᠈Ȧ	᠈Ḋ	᠈◁̇
z / s	ᵰ	ᓭ	ᓯ	ᓱ	ᓴ	ᓯ̇	ᓱ̇	ᓴ̇
zw / sw		·ᓭ	·ᓯ	·ᓱ	·ᓴ	·ᓯ̇	·ᓱ̇	·ᓴ̇
y	°	ᔦ	ᔨ	ᔪ	ᔭ	ᔨ̇	ᔪ̇	ᔭ̇

Consonant Key(s)	Vowel Key(s)							
		e	i	o	a	ii	oo	aa
yw		ᐧ᎓	ᐧ᎐	ᐧᐸ	ᐧ᎒	ᐧ᎐̇	ᐧᐸ̇	ᐧ᎒̇
w	°	▽	ᐧ△	ᐧ▷	ᐧ◁	△̇	▷̇	ᐧ◁̇
h	‖	"▽	"△	"▷	"◁	"△̇	"▷̇	"◁̇
f	�	ᕗ	ᕐ	ᕝ	ᕞ	ᕗ̇	ᕝ̇	ᕞ̇
fw								ᐧᕞ̇
] (Right Bracket)	z	ᒉ	ᒍ	ᒎ	ᒣ			
\ (Backslash)	s	ᒧ	ᒣ	ᒡ	ᒪ			
- (Hyphen)	ᐠ	ᒉ	ᒥ	ᒍ	ᒣ	ᒋ̇	ᒍ̇	ᒣ̇
-w (Hyphen + w)		ᐧᒉ	ᐧᒥ	ᐧᒍ	ᐧᒣ	ᐧᒋ̇	ᐧᒍ̇	ᐧᒣ̇
= (Equal sign)	ᔾ	ᒧ	ᒣ	ᑭ	ᑫ	ᑎ̇	ᑭ̇	ᑫ̇
=w (Equal + w)								ᐧᑫ̇

Shifted

*Use the unshifted w for syllables that need the w-dot

Consonant Key(s)	Vowel Key(s)							
		e	i	o	a	ii	oo	aa
W	ᐧᐃ							
R	�							
L	�							
T	�	ᒐ	ᒣ	ᒍ	ᒉ	ᒑ́	ᒎ̇	ᒣ̇
Tw								ᐧᒣ̇
Z / S	ᴜ	ᓀ	ᓂ	ᓄ	ᓇ	ᓃ̇	ᓅ̇	ᓈ̇
Zw / Sw		ᐧᓀ	ᐧᓂ	ᐧᓄ	ᐧᓇ	ᐧᓃ̇	ᐧᓅ̇	ᐧᓈ̇
C	‐	ᕐ	ᕑ	ᕒ	ᕓ	ᕔ̇	ᕕ̇	ᕖ̇
Cw		ᐧᕐ	ᐧᕑ	ᐧᕒ	ᐧᕓ	ᐧᕔ̇	ᐧᕕ̇	ᐧᕖ̇

Punctuation

Key(s)	Output
q	ᐧ (w-dot)
. (Period)	x
Right-Alt / Option + . (Period)	.
[(Left Bracket)	Used to insert a false space so that words like ᐊᐊ (a'a) can be typed correctly
Right-Alt / Option + [(Left Bracket)	[
Right-Alt / Option +] (Right Bracket)	]
Right-Alt / Option + - (Hyphen)	-
Right-Alt / Option + = (Equal Sign)	=

Right-Alt / **Option** + **;** (Semicolon)	‹
Shift + **Right-Alt** / **Option** + **;** (Semicolon)	«
Right-Alt / **Option** + **'** (Quote)	›
Shift + **Right-Alt** / **Option** + **'** (Quote)	»
` (Backquote)	˙ (long vowel dot)
Right-Alt / **Option** + **`** (Backquote)	`

Other

- All English letters can be typed by pressing **Right-Alt / Option** followed by the letter or letters you wish to type
- All uppercase English letters can by typed by pressing **Right-Alt / Option + Shift** followed by the letter or letters you wish to type