

How WasteFlow Works

Simple explanation of the whole system — who does what, how drivers are created, and how the website and phone app stay connected.

1. Big picture (one system, two apps)

WasteFlow is a waste-collection tracking system. There is **one shared database** and **two apps** that use it.

SYSTEM CONNECTION MAP

WasteFlow ERP

Website for office staff
`wasteflow-drab.vercel.app`

Shared Database

Supabase (cloud)
Same data for everyone

Driver App

Phone app for drivers
Expo / mobile

Office plans work on the website → Drivers do work on the phone → Both see the same live data

2. The four roles

Role	Where they work	What they do
Admin	ERP website	Full control — staff, routes, vehicles, settings, deletes
Supervisor	ERP website	Daily operations — routes, board, tracking, assignments
Driver	Driver phone app	Start trips, collect stops, GPS, photos, finish trips
Field Worker	ERP (scanner / field)	Scan QR codes, enter waste quantities on site

Important: The phone Driver App only allows accounts with role *driver*. Admins and supervisors must use the ERP website.

3. Static demo logins vs real (dynamic) staff

Already set up (demo)

- `admin@wasteflow.app` / `Admin123!` → Admin (ERP)
- `driver@wasteflow.app` / `Driver123!` → Driver EMP-003 (phone)

Use these to try the system quickly.

Real staff (dynamic)

- Create a login (email + password or Google)
- Create an Employee row in ERP
- Link the email so the phone app knows who they are

This is how you add new drivers for a client.

4. How to make a new driver (exact flow)

Two pieces must connect: a **login** and an **employee profile**.

CREATE A DRIVER — STEP BY STEP


- 1 Create a login**
In Supabase Auth (or Google sign-in), create email + password for the person. Example:
`ram.driver@city.gov` / a temporary password.
- 2 Open ERP → Employees → Add employee**
Fill name, Employee ID (EMP-00x), set Role = **Driver**, assign a **Route** and **Vehicle**.
- 3 Link auth account (email)**
Type the same email as their login. This attaches the employee to that login so the Driver App can load their route and start trips.
- 4 Driver opens the phone app**
They sign in with that email + password (or Google). App checks: role = driver + employee linked → shows their assigned work.

What “Link auth account” means: Employee record = job profile (route, vehicle). Auth account = ability to log in. The link field joins them. Without it, login works but the app says “No employee profile — ask admin to link you.”

LOGIN ↔ EMPLOYEE CONNECTION



5. Who assigns work, who does it, who watches



6. What each ERP screen is for

Screen	Purpose (plain English)
Dashboard	Today's health check — scheduled, collected %, missed, diesel, vehicles
QR Scanner	Scan a generator QR and record a collection from the office/field
Collection & Tracking	Trips, daily stop status board, GPS trail
Bulk Waste Generators	Master list of hotels/malls/sites + QR codes
Routes	Ordered stops for each route; generate today's plan
Employees	Staff list, roles, route/vehicle assign, link login email
Vehicles	Fleet list, capacity, odometer, assigned driver
Diesel Log	Fuel entries and abnormal usage flags
Waybills	Trip paperwork (numbers, km, totals)
Waste Types	Wet / dry / reject categories used in collection
Reports	Summaries and analytics
Settings	Roles and admin tools

7. What the Driver App does



- Only drivers can use it
- Shows assigned route(s) and vehicle
- Records quantities, photos, and GPS
- Can queue work offline and sync later

8. Setup order (first-time client)



9. One-sentence summary

Admin/Supervisor plan people, routes, and today's work in the ERP website; Drivers carry out that work in the phone app; everyone reads and writes the same database so the office sees fieldwork in real time.