
Step 6 — Instruments and drums (wizard step 4)

Goal: give each track a Minecraft sound.



Instrument setup

1. Each track automatically gets a sound from its **General MIDI instrument number**, with a fixed table of the 128 instruments, like Note Block Studio's MIDI import (see the table at the bottom of this guide): for example no. 1 piano → harp, no. 33 to 40 (basses) → double bass, no. 41 violin → flute. The track name and its notes do not matter. The reason is written under the sound.
2. To change it: choose another sound in the catalog on the right (search box, categories, **Listen**), then click **Assign the selected sound to the track**.
3. Adjust the **Relative volume** and the **Transposition** (in semitones) of the track.
4. **Lowest note / Highest note** let you hear the extremes of the track with the chosen sound.

Drum tracks

A percussion track uses a **key → sound** table: each drum key (kick, snare, hi-hat…) is linked to a sound and a transposition, the way Note Block Studio creators do it. Keys without a sound can be ignored or played with the snare drum. **Restore the default table** undoes your changes.

Sounds available

- **Note blocks** (official Minecraft files: those of your installation, or downloaded from Mojang).
- **Mob sounds** of the selected Minecraft version, sorted by category (voice, hurt, movement…).
- **Custom sounds** placed in the Note Block Studio `Custom` folder (full edition, if Note Block Studio is installed).

> **Free edition:** 8 basic note block instruments (no pling, bell, chime, flute, guitar, xylophones or bit), and only the voices of 3 farm animals for mob sounds.

Table of the 128 General MIDI instruments

In the free edition, a sound reserved for the full edition is replaced by the closest free sound (often the harp).

No.	General MIDI	Note block
1	Acoustic grand piano	Harp (piano)
2	Bright acoustic piano	Harp (piano)
3	Electric grand piano	Pling (electric piano)
4	Honky-tonk piano	Harp (piano)
5	Electric piano 1	Pling (electric piano)
6	Electric piano 2	Pling (electric piano)
7	Harpsichord	Harp (piano)
8	Clavinet	Pling (electric piano)
9	Celesta	Bell (glockenspiel)
10	Glockenspiel	Bell (glockenspiel)

No.	General MIDI	Note block
11	Music box	Bell (glockenspiel)
12	Vibraphone	Vibraphone (iron xylophone)
13	Marimba	Xylophone
14	Xylophone	Xylophone
15	Tubular bells	Chime
16	Dulcimer	Harp (piano)
17	Drawbar organ	Bit (square wave)
18	Percussive organ	Bit (square wave)
19	Rock organ	Bit (square wave)
20	Church organ	Flute
21	Reed organ	Flute
22	Accordion	Flute
23	Harmonica	Flute
24	Tango accordion	Flute
25	Nylon guitar	Guitar
26	Steel guitar	Guitar
27	Jazz guitar	Guitar
28	Clean electric guitar	Guitar
29	Muted electric guitar	Guitar
30	Overdriven guitar	Guitar
31	Distortion guitar	Guitar
32	Guitar harmonics	Guitar

No.	General MIDI	Note block
33	Acoustic bass	Double bass
34	Electric bass (finger)	Double bass
35	Electric bass (pick)	Double bass
36	Fretless bass	Double bass
37	Slap bass 1	Double bass
38	Slap bass 2	Double bass
39	Synth bass 1	Double bass
40	Synth bass 2	Double bass
41	Violin	Flute
42	Viola	Flute
43	Cello	Double bass
44	Contrabass	Double bass
45	Tremolo strings	Flute
46	Pizzicato strings	Harp (piano)
47	Orchestral harp	Harp (piano)
48	Timpani	Bass drum
49	String ensemble 1	Harp (piano)
50	String ensemble 2	Harp (piano)
51	Synth strings 1	Pling (electric piano)
52	Synth strings 2	Pling (electric piano)
53	Choir aahs	Flute
54	Voice oohs	Flute

No.	General MIDI	Note block
55	Synth voice	Pling (electric piano)
56	Orchestra hit	Bit (square wave)
57	Trumpet	Bit (square wave)
58	Trombone	Didgeridoo
59	Tuba	Didgeridoo
60	Muted trumpet	Bit (square wave)
61	French horn	Flute
62	Brass section	Bit (square wave)
63	Synth brass 1	Bit (square wave)
64	Synth brass 2	Bit (square wave)
65	Soprano sax	Flute
66	Alto sax	Flute
67	Tenor sax	Flute
68	Baritone sax	Didgeridoo
69	Oboe	Flute
70	English horn	Flute
71	Bassoon	Didgeridoo
72	Clarinet	Flute
73	Piccolo	Flute
74	Flute	Flute
75	Recorder	Flute
76	Pan flute	Flute

No.	General MIDI	Note block
77	Blown bottle	Flute
78	Shakuhachi	Flute
79	Whistle	Flute
80	Ocarina	Flute
81	Square lead	Bit (square wave)
82	Sawtooth lead	Bit (square wave)
83	Calliope lead	Flute
84	Chiff lead	Flute
85	Charang lead	Guitar
86	Voice lead	Pling (electric piano)
87	Fifths lead	Bit (square wave)
88	Bass + lead	Bit (square wave)
89	New age pad	Pling (electric piano)
90	Warm pad	Pling (electric piano)
91	Polysynth pad	Pling (electric piano)
92	Choir pad	Flute
93	Bowed pad	Pling (electric piano)
94	Metallic pad	Vibraphone (iron xylophone)
95	Halo pad	Pling (electric piano)
96	Sweep pad	Pling (electric piano)
97	Rain FX	Chime
98	Soundtrack FX	Pling (electric piano)

No.	General MIDI	Note block
99	Crystal FX	Chime
100	Atmosphere FX	Pling (electric piano)
101	Brightness FX	Bell (glockenspiel)
102	Goblins FX	Pling (electric piano)
103	Echoes FX	Chime
104	Sci-fi FX	Bit (square wave)
105	Sitar	Banjo
106	Banjo	Banjo
107	Shamisen	Banjo
108	Koto	Harp (piano)
109	Kalimba	Vibraphone (iron xylophone)
110	Bagpipe	Didgeridoo
111	Fiddle	Flute
112	Shanai	Flute
113	Tinkle bell	Bell (glockenspiel)
114	Agogo	Cow bell
115	Steel drums	Vibraphone (iron xylophone)
116	Woodblock	Hi-hat (click)
117	Taiko drum	Bass drum
118	Melodic tom	Bass drum
119	Synth drum	Bass drum
120	Reverse cymbal	Snare drum

No.	General MIDI	Note block
121	Guitar fret noise	Hi-hat (click)
122	Breath noise	Snare drum
123	Seashore	Snare drum
124	Bird tweet	Flute
125	Telephone ring	Bell (glockenspiel)
126	Helicopter	Snare drum
127	Applause	Snare drum
128	Gunshot	Snare drum

Next guide: preview and samples.