
GIT PUSH THE BEATS

Melody Dive Use-Case Specification: View Lyrics

Version 1.0

Melody Dive	Version: 1.0
Use-Case Specification: View Lyrics	Date: 17/11/2025
UC ViewLyrics	

Revision History

Date	Version	Description	Author
17/11/2025	1.0	Add use-case specification: view lyrics	Nguyễn Hoàng Đăng

Melody Dive	Version: 1.0
Use-Case Specification: View Lyrics	Date: 17/11/2025
UC ViewLyrics	

Table of Contents

1. Use-Case Name: View Lyrics	4
1.1 Brief Description	4
2. Flow of Events	4
2.1 Basic Flow	4
2.2 Alternative Flows	4
2.2.1 Lyrics Not Available	4
2.2.2 User Scrolls or Pauses Playback	5
3. Special Requirements	5
3.1 Synchronized Lyrics	5
3.2 Static Lyrics Fallback	5
3.3 Non-interruptive Display	5
3.4 Quick Exit	5
4. Preconditions	5
4.1 Active Playback	5
4.2 Lyrics Availability	5
5. Postconditions	5
5.1 Lyrics Displayed	5
5.2 Continuous Playback	5
5.3 Manual Scroll/Sync Maintained	5
5.4 No Lyrics Available	5
6. Extension Points	5
6.1 Language Selection	5
6.2 Toggle Full-Screen/Mini-Player View	5
6.3 Download Lyrics	6

Melody Dive	Version: 1.0
Use-Case Specification: View Lyrics	Date: 17/11/2025
UC ViewLyrics	

Use-Case Specification: View Lyrics


1. Use-Case Name: View Lyrics

1.1 Brief Description

This use case allows the user to view the lyrics of the currently playing track. Lyrics may be displayed in real-time synchronized with playback (if available) or as static text. The user can access lyrics from the full-screen player interface without interrupting audio playback.

2. Flow of Events

2.1 Basic Flow



1. System displays a mini bar at the bottom of the screen when a track is playing.
2. User taps the “Lyrics” button in the player interface.
3. System checks if lyrics are available for the current track.
4. System displays the lyrics:
 - Synchronized with playback if available.
 - Static text if only plain lyrics exist.
5. User scrolls through lyrics manually if desired.
6. User exits lyrics view by tapping a close button or navigating back.
7. Flow ends when the user leaves the lyrics view.

2.2 Alternative Flows

2.2.1 Lyrics Not Available

- At step 2, this alt flow occurs here if the system finds no lyrics
- System displays a message such as “Lyrics not available.”
- User can return to the player or continue playback..

Melody Dive	Version: 1.0
Use-Case Specification: View Lyrics	Date: 17/11/2025
UC ViewLyrics	

2.2.2 *User Scrolls or Pauses Playback*

- At step 5, this alt flow may occur here if the user manually scroll the lyric or pause playback.
- System continues playback without interrupting the lyrics view.
- User can toggle automatic scroll/sync back on if desired.

3. **Special Requirements**

3.1 **Synchronized Lyrics**

If available, lyrics must scroll automatically in sync with the playback of the track.

3.2 **Static Lyrics Fallback**

If synchronization data is not available, lyrics must still be displayed as static text.

3.3 **Non-interruptive Display**

Viewing lyrics must not stop or pause the current playback.

3.4 **Quick Exit**

The user must be able to exit the lyrics view easily, returning to mini-player or previous screen without disrupting playback.

4. **Preconditions**

4.1 **Active Playback**

A track must be currently playing in the music player.

4.2 **Lyrics Availability**

The system should have lyrics data (synchronized or static) for the selected track, or be able to indicate unavailability.

5. **Postconditions**

5.1 **Lyrics Displayed**

Lyrics are visible to the user in synchronized or static format.

5.2 **Continuous Playback**

Audio playback continues uninterrupted while the lyrics view is open.

5.3 **Manual Scroll/Sync Maintained**

User's scrolling or sync preferences are applied correctly during playback.

5.4 **No Lyrics Available**

If lyrics are unavailable, a message such as "Lyrics not available" is shown.

6. **Extension Points**

6.1 **Language Selection**

- Location in the basic flow: step 4.
- Triggered when multiple lyric languages are available.
- User selects a preferred language, and the system updates the displayed lyrics without interrupting playback.

6.2 **Toggle Full-Screen/Mini-Player View**

- Location in the basic flow: step 4.
- Triggered when the user switches between full-screen lyrics and mini player.
- Playback continues seamlessly while updating the UI layout.

Melody Dive	Version: 1.0
Use-Case Specification: View Lyrics	Date: 17/11/2025
UC ViewLyrics	

6.3 Download Lyrics

- Location in the basic flow: step 4.
- Triggered when the user taps a “Download” button in the lyrics view.
- The system generates a text file containing the lyrics and prompts the user to save it locally without interrupting playback.