



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout



Categories

A->Z

System Core >

Analog >

Timers >

Connectivity >

CAN

I2C1

☒ I2C2

SPI1

SPI2

USART1

USART2

USART3

USB

Computing >

Middleware and Software Packs >

I2C2 Mode and Configuration

Mode

I2C

I2C

Configuration

Reset Configuration

☒ NVIC Settings☒ DMA Settings☒ GPIO Settings☒ Parameter Settings☒ User Constants

Configure the below parameters :



Master Features

I2C Speed Mode

Standard Mode

I2C Clock Speed (Hz)

100000


Slave Features

Clock No Stretch Mode

Disabled

Pinout view

System view





Pinout & Configuration

Clock Configuration

Project Manager

Tools

▼ Software Packs

▼ Pinout

Categories A->Z

System Core >

Analog >

Timers ▼

RTC

TIM1

TIM2

☒ TIM3

TIM4

Connectivity ▼

CAN

I2C1

☒ I2C2

SPI1

SPI2

USART1

☒ USART2☒ USART3

USB

Computing >

Middleware and Software Packs >

TIM3 Mode and Configuration

Mode

Slave Mode Trigger Source ☒ Internal ClockChannel1 Channel2 Channel3 Channel4 Combined Channels ☐ XOR activation☐ One Pulse Mode

Configuration


Reset Configuration

☒ Parameter Settings ☒ User Constants ☒ NVIC Settings ☒ DMA Settings

NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
TIM3 global interrupt	☒	0	0

Pinout view

System view



Search

10:48 AM
7/2/2026



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

Q [v]

Categories

A->Z

System Core >

Analog >

Timers >

RTC

TIM1

TIM2

TIM3

TIM4

Connectivity >

CAN

I2C1

I2C2

SPI1

SPI2

USART1

USART2

USART3

USB

Computing >

Middleware and Software Packs >

TIM3 Mode and Configuration

Mode

Slave Mode Disable

Trigger Source Disable

☒ Internal Clock

Channel1 Disable

Channel2 Disable

Channel3 Disable

Channel4 Disable

Combined Channels Disable

☐ XOR activation☐ One Pulse Mode

Configuration

Reset Configuration

☒ Parameter Settings ☒ User Constants ☒ NVIC Settings ☒ DMA Settings

Configure the below parameters :

Q Search (Ctrl+F)

Counter Settings

Prescaler (PSC - 16 bits value) 7999

Counter Mode Up

Counter Period (AutoReload Register) 499

Counter Period (AutoReload Register - 16 bits value)

Counter Period (AutoReload Register - 16 bits value) must be between 0 and 65 535

Pinout view

System view

