IE6700 Data Management for Analytics Milestone: Logical Model (Relational model)

Group 5

Student 1: Aliya LNU

Student 2: Nixon Lobo

6315389069 (Tel of Student 1)

8573209201 (Tel of Student 2)


Lnu.ali@northeastern.edu
Lobo.ni@northeastern.edu

Percentage of Effort Contributed by Student1: 50%

Percentage of Effort Contributed by Student2: 50%

Signature of Student 1: Aliya LNU Signature of Student 2: Nixon Lobo

Submission Date: 03/03/2024



USER (UserID, userName, userEmail, userAddress, userPhoneNr)

COMMERICIAL (VAT, UserID)

- UserID foreign key refers to UserID in USER, NULL ALLOWED

ORDER (OrderID, amount, orderStatus, orderDate, DeliveryNr, WarehosueID)

- DeliveryNr foreign key refers to DeliveryNr in DELIVERY, NULL ALLOWED
- WarehosueID foreign key refers to WarehosueID in INVENTORY, NULL ALLOWED

SUBSCRIPTION (SubID, startDate, endDate, frequency, status, UserID, OrderID)

- UserID foreign key refers to UserID in USER, NULL ALLOWED
- OrderID foreign key refers to OrderID in ORDER, NULL ALLOWED

EXTRA_ITEM (*UserID*, *OrderID*)

- UserID foreign key refers to UserID in USER, NULL ALLOWED
- OrderID foreign key refers to OrderID in ORDER, NULL ALLOWED

FEEDBACK (fbID, rating, comments, date, UserID, OrderID)

- UserID foreign key refers to UserID in USER, NULL ALLOWED
- OrderID foreign key refers to OrderID in ORDER, NULL ALLOWED

PAYMENT (PayNr, DueDate, amount, OrderID)

- OrderID foreign key refers to OrderID in ORDER, NULL ALLOWED

PROMOTION (PromotionID, name, description, VaildFrom, VaildTo, OrderID)

- OrderID foreign key refers to OrderID in ORDER, NULL ALLOWED

DELIVERY (<u>DeliveryNr</u>, StartLoc, EndLoc, Distances, ETA, *PlateNr*, *DriverID*)

- OrderID foreign key refers to OrderID in ORDER, NULL ALLOWED
- PlateNr foreign key refers to PlateNr in VEHICLE, NULL ALLOWED
- DriverID foreign key refers to DriverID in DRIVER, NULL ALLOWED

VEHICLE (<u>PlateNr</u>, DeliveryNr)

- DeliveryNr foreign key refers to DeliveryNr in DELIVERY, NULL ALLOWED

DRIVER (DriverID, name, licenseNr, availability)

DRIVES (PlateNr, DriverID)

- PlateNr foreign key refers to PlateNr in VEHICLE, NULL ALLOWED
- DriverID foreign key refers to DriverID in DRIVER, NULL ALLOWED

INVENTORY (<u>WarehosueID</u>, name, location, capacity)

PRODUCT (<u>ProductID</u>, name, price, category, expireDate)

SUPPLIER (SupplierID, VAT, name, phoneNr, address, email)

STORE (WarehosueID, ProductID)

- WarehosueID foreign key refers to WarehosueID in INVENTORY, NULL ALLOWED
- ProductID foreign key refers to ProductID in INVENTORY, NULL ALLOWED

SUPPLY (SupplierID, ProductID)

- SupplierID foreign key refers to SupplierID in SUPPLIER, NULL ALLOWED
- ProductID foreign key refers to ProductID in INVENTORY, NULL ALLOWED