

Unit 4: Project 3, a troubleshooting email

Subject: Steps to restore your monitor's audio

Hi Rosario,

I am writing to you because I've heard that you're currently experiencing a problem with your computer and that because of it you can't hear any audio playback. The thing is that it so happens that some time ago I experienced that same problem with my own work computer and managed to solve it after some time, so I thought of writing to you to tell you what I did to solve it and save you some time.

Based on the details I've managed to gather about your issue, it seems that you recently changed your monitor's HDMI cable, and what most likely has happened is that your computer has reverted to its default audio settings, just as I experienced in the past. I'll go over the exact troubleshooting steps that I went through to solve the problem later, but for now I'll just quickly tell you that the problem is that your computer's operating system has basically "forgotten" that the monitor was the preferred audio output, and instead it has changed the output to something else.

To get the sound coming out from your monitor again as you prefer, please follow these detailed troubleshooting steps in order, which for me solved the problem:

1. Go to your desktop, minimizing any open windows that you may have so you have a clear sight of it.
2. Locate the taskbar by moving your cursor to the very bottom right corner of the desktop where the time and date are displayed.
3. Once there, find the volume control; it resembles a small speaker.
4. Then open the audio menu by left-clicking that same speaker icon from the previous step, which will make a small panel pop up showing a volume slider.
5. There you must check your current output audio device, which will be displayed just on top of the slider. If the problem that you're experiencing is the same as I had, it will probably say something like "Realtek (R) Audio" or similar, confirming that the audio is being sent to the wrong place.
6. Then you should expand the available devices list by clicking on the name "Realtek" (or whatever it said) or by clicking on the small arrow pointing upward next to it.
7. Finally, you'll see on that list your monitor; to restore its audio, all you have to do is click it.

All these steps should have managed to fix your issue, and if that is the case, please reply back to me telling me it worked, or tell me at the office if you prefer. But if the problem is still there, which is possible, being that there are a lot of variables and things that could be different on your computer, or if you find the written steps a bit difficult to follow, then you can either contact back or see this YouTube video where this very problem is addressed in more detail and in a visual way: [YouTube Video](#)

Best regards,

Álvaro Jiménez Muñoz, IT Department