```
root@kali: /home/aman_singhal
Session  Actions  Edit  View  Help

┌──(root㉿kali)-[/home/aman_singhal]
└─# pwd
/home/aman_singhal

┌──(root㉿kali)-[/home/aman_singhal]
└─# ls
Desktop  Documents  Downloads  Music  Pictures  Public  Templates  Videos

┌──(root㉿kali)-[/home/aman_singhal]
└─# whoami
root

┌──(root㉿kali)-[/home/aman_singhal]
└─# date
Wed Feb 25 07:08:38 AM EST 2026

┌──(root㉿kali)-[/home/aman_singhal]
└─# uptime
 07:08:41 up 22 min,  1 user,  load average: 0.00, 0.01, 0.06

┌──(root㉿kali)-[/home/aman_singhal]
└─#
```

```
root@kali: ~
Session  Actions  Edit  View  Help

┌──(root㉿kali)-[/home/aman_singhal]
└─# cd /home

┌──(root㉿kali)-[/home]
└─# cd ~

┌──(root㉿kali)-[~]
└─#
```

```
root@kali: ~
Session  Actions  Edit  View  Help
LS(1)                          User Commands                          LS(1)

NAME
       ls - list directory contents

SYNOPSIS
       ls [OPTION]... [FILE]...

DESCRIPTION
       List  information about the FILEs (the current directory by default).
       Sort entries alphabetically if none of -cftuvSUX nor --sort is speci-
       fied.

       Mandatory arguments to long options are mandatory for  short  options
       too.

       -a, --all
              do not ignore entries starting with .

       -A, --almost-all
              do not list implied . and ..

       --author
              with -l, print the author of each file

       -b, --escape
              print C-style escapes for nongraphic characters
 Manual page ls(1) line 1 (press h for help or q to quit)
```

```
root@kali: ~
Session  Actions  Edit  View  Help

┌──(root㉿kali)-[~]
└─# ls --help
Usage: ls [OPTION]... [FILE]...
List information about the FILEs (the current directory by default).
Sort entries alphabetically if none of -cftuvSUX nor --sort is specified.

Mandatory arguments to long options are mandatory for short options too.
  -a, --all                  do not ignore entries starting with .
  -A, --almost-all           do not list implied . and ..
      --author               with -l, print the author of each file
  -b, --escape               print C-style escapes for nongraphic characters
      --block-size=SIZE      with -l, scale sizes by SIZE when printing them;
                             e.g., '--block-size=M'; see SIZE format below

  -B, --ignore-backups       do not list implied entries ending with ~
  -c                         with -lt: sort by, and show, ctime (time of last
                             change of file status information);
                             with -l: show ctime and sort by name;
                             otherwise: sort by ctime, newest first

  -C                         list entries by columns
      --color[=WHEN]         color the output WHEN; more info below
  -d, --directory            list directories themselves, not their contents
  -D, --dired                generate output designed for Emacs' dired mode
  -f                         same as -a -U
  -F, --classify[=WHEN]      append indicator (one of */=>@|) to entries WHEN
      --file-type            likewise, except do not append '*'
```

```
root@kali: ~
Session  Actions  Edit  View  Help
┌──(root㉿kali)-[~]
└─# systemctl --help
systemctl [OPTIONS ... ] COMMAND  ...

Query or send control commands to the system manager.

Unit Commands:
  list-units [PATTERN ... ]             List units currently in memory
  list-automounts [PATTERN ... ]        List automount units currently in memo>
                                        ordered by path
  list-paths [PATTERN ... ]             List path units currently in memory,
                                        ordered by path
  list-sockets [PATTERN ... ]           List socket units currently in memory,
                                        ordered by address
  list-timers [PATTERN ... ]            List timer units currently in memory,
                                        ordered by next elapse
  is-active PATTERN ...                 Check whether units are active
  is-failed [PATTERN ... ]              Check whether units are failed or
                                        system is in degraded state
  status [PATTERN ... |PID ... ]        Show runtime status of one or more uni>
  show [PATTERN ... |JOB ... ]          Show properties of one or more
                                        units/jobs or the manager
  cat PATTERN ...                       Show files and drop-ins of specified u>
  help PATTERN ... |PID ...             Show manual for one or more units
  list-dependencies [UNIT ... ]         Recursively show units which are requi>
                                        or wanted by the units or by which tho>
                                        units are required or wanted
  start UNIT ...                        Start (activate) one or more units
```

```
root@kali: ~
Session  Actions  Edit  View  Help

┌──(root㉿kali)-[~]
└─# systemctl get-default
graphical.target

┌──(root㉿kali)-[~]
└─#
```