Connect a USB webcam to your computer

Connect a USB webcam to your computer, install any required drivers, and verify that the webcam works by opening the default camera app and capturing a photo.



Made with GAMMA

Answer: connect a USB webcam

1. Plug the webcam's USB cable into a free USB port on your computer.
2. Wait while Windows installs the driver automatically. If it does not, install the driver from the manufacturer's website or the included disc.
3. Open the Camera app from the Start menu.
4. Check that the webcam preview appears, then click the camera button to take a photo.
5. Open Pictures > Camera Roll to find your photo and confirm the webcam works.

Made with GAMMA



Set up a local printer (USB or network)

Set up a local printer (USB or network), install the correct driver, and print a test page to confirm successful installation.

Made with GAMMA

Answer: set up a local printer

1. Connect the printer with USB, or make sure it is on the same network as your computer.
2. Open Settings > Bluetooth & devices > Printers & scanners.
3. Click Add device and select your printer from the list.
4. If Windows cannot find the right driver, install the correct driver from the manufacturer's website.
5. Open the printer's properties and click Print Test Page to confirm it works.

Made with GAMMA

Simulate a connectivity issue by unplugging the printer's USB cable

Simulate a connectivity issue by unplugging the printer’s USB cable, then use Windows Device Manager to identify and resolve the ’printer not detected’ problem.

Hint: *Check for error icons and use the ’Scan for hardware changes’ option after reconnecting.*




Made with GAMMA

Answer: printer not detected in Device Manager

1. Unplug the printer's USB cable, then plug it back in.
2. Open Device Manager (right-click Start and select it).
3. Look for a device with a yellow warning icon or an Unknown device entry.
4. Click Action > Scan for hardware changes.
5. If the device is still flagged, right-click it, select Update driver, or uninstall it and reinstall the correct driver.

Made with GAMMA



A user reports that their webcam video is not displaying in Zoom

A user reports that their webcam video is not displaying in Zoom, but it works in the default camera app. Troubleshoot and resolve the issue so the webcam works in both applications.

Hint: *Check if another app is using the webcam or if Zoom permissions are enabled.*

Made with GAMMA

Answer: webcam not showing in Zoom

1. Close other apps that may be using the camera, such as Teams, Skype, or browser tabs.
2. Open Windows Settings > Privacy & security > Camera and turn on camera access and allow desktop apps to use the camera.
3. In Zoom, open Settings > Video and choose your webcam from the Camera list.
4. Restart Zoom.
5. If the video still does not appear, update the webcam driver in Device Manager.

Made with GAMMA