




### Router0

Physical Config CLI Attributes

#### IOS Command Line Interface

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

```
Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface gig0/0
Router(config-if)#ip address 192.168.1.1 255.255.255.0
Router(config-if)#no shutdown
```

```
Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up
```

```
Router(config-if)#exit
Router(config)#interface gig0/1
Router(config-if)#ip address 192.168.2.1 255.255.255.0
Router(config-if)#no shutdown
```

```
Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up
```

```
Router(config-if)#exit
Router(config)#
```

```
Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#access-list 10 deny 192.168.1.40 0.0.0.0
```

```
% Invalid input detected at '^' marker.
```

```
Router(config)#access-list 10 deny 192.168.1.40 0.0.0.0
Router(config)#permit-list permit any
```

```
% Invalid input detected at '^' marker.
```

```
Router(config)#access-list 10 permit any
```

```
% Invalid input detected at '^' marker.
```

```
Router(config)#access-list 10 permit any
Router(config)#interface gig0/0
Router(config-if)#ip access-group 10 in
Router(config-if)#exit
Router(config)#
```

## Command Prompt

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 192.168.2.100

Pinging 192.168.2.100 with 32 bytes of data:

Reply from 192.168.2.100: bytes=32 time<1ms TTL=127
Reply from 192.168.2.100: bytes=32 time<1ms TTL=127
Reply from 192.168.2.100: bytes=32 time<1ms TTL=127
Reply from 192.168.2.100: bytes=32 time<1ms TTL=127

Ping statistics for 192.168.2.100:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>ping 192.168.2.100

Pinging 192.168.2.100 with 32 bytes of data:

Reply from 192.168.1.1: Destination host unreachable.
Reply from 192.168.1.1: Destination host unreachable.
Reply from 192.168.1.1: Destination host unreachable.
Reply from 192.168.1.1: Destination host unreachable.

Ping statistics for 192.168.2.100:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

C:\>
```

## Command Prompt

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 192.168.2.100

Pinging 192.168.2.100 with 32 bytes of data:

Reply from 192.168.2.100: bytes=32 time<1ms TTL=127
Reply from 192.168.2.100: bytes=32 time<1ms TTL=127
Reply from 192.168.2.100: bytes=32 time<1ms TTL=127
Reply from 192.168.2.100: bytes=32 time<1ms TTL=127

Ping statistics for 192.168.2.100:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>ping 192.168.2.100

Pinging 192.168.2.100 with 32 bytes of data:

Reply from 192.168.2.100: bytes=32 time<1ms TTL=127
Reply from 192.168.2.100: bytes=32 time<1ms TTL=127
Reply from 192.168.2.100: bytes=32 time<1ms TTL=127
Reply from 192.168.2.100: bytes=32 time<1ms TTL=127

Ping statistics for 192.168.2.100:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>
```

```
Router>EN
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#access-list 100 permit tcp host 192.168.1.10 host 192.168.2.100 eq 80
Router(config)#access-list 100 permit tcp host 192.168.1.30 host 192.168.2.100 eq 21
Router(config)#access-list 100 permit ip any any
Router(config)#interface gig0/0
Router(config-if)#no ip access-group 10 in
Router(config-if)#ip access-group 100 in
Router(config-if)#exit
Router(config)#
```

### PC3

Physical Config **Desktop** Programming Attributes

#### Command Prompt

```
Pinging 192.168.2.100 with 32 bytes of data:

Reply from 192.168.2.100: bytes=32 time<1ms TTL=127
Reply from 192.168.2.100: bytes=32 time<1ms TTL=127
Reply from 192.168.2.100: bytes=32 time<1ms TTL=127
Reply from 192.168.2.100: bytes=32 time<1ms TTL=127

Ping statistics for 192.168.2.100:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>ping 192.168.2.100

Pinging 192.168.2.100 with 32 bytes of data:

Reply from 192.168.1.1: Destination host unreachable.
Reply from 192.168.1.1: Destination host unreachable.
Reply from 192.168.1.1: Destination host unreachable.
Reply from 192.168.1.1: Destination host unreachable.

Ping statistics for 192.168.2.100:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

C:\>ftp 192.168.2.100
Trying to connect...192.168.2.100
Connected to 192.168.2.100
220- Welcome to PT Ftp server
Username:

%Error ftp://192.168.2.100/ (No such Account)
332- Need account for login
```

### PC0

Physical Config **Desktop** Programming Attributes

#### Web Browser

< > URL  Go Stop

## Cisco Packet Tracer

Welcome to Cisco Packet Tracer. Opening doors to new opportunities. Mind Wide Open.

Quick Links:

[A small page](#)  
[Copyrights](#)  
[Image page](#)  
[Image](#)