2CEIT503 COMPUTER NETWORKS

Practical: 8

AIM- Define a topology with four nodes in which one node act that forwards the data that two nodes are sending to the fourth node. Also find a way to distinguish the data flows from the two nodes other, and learn how a queue can be monitored to see how full it is and how many packets are being discarded.

Submitted By: 21012021003_AMIT GOSWAMI



Department of Computer

Engineering/Information Technology

Example2.tcl

```
#Create a simulator object
set ns [new Simulator]
#Define different colors for data flows
$ns color 1 Blue
$ns color 2 Red
#Open the nam trace file
set nf [open out.nam w]
$ns namtrace-all $nf
#Define a 'finish' procedure
proc finish { } {
    global ns nf
    $ns flush-trace
   #Close the trace file
    close $nf
   #Execute nam on the trace file
    exec nam out.nam &
    exit 0
}
#Create four nodes
set n0 [$ns node]
set n1 [$ns node]
set n2 [$ns node]
set n3 [$ns node]
#Create links between the nodes
$ns duplex-link $n0 $n2 1Mb 10ms DropTail
$ns duplex-link $n1 $n2 1Mb 10ms DropTail
$ns duplex-link $n3 $n2 1Mb 10ms SFQ
$ns duplex-link-op $n0 $n2 orient right-down
$ns duplex-link-op $n1 $n2 orient right-up
$ns duplex-link-op $n2 $n3 orient right
#Monitor the queue for the link between node 2 and node 3
$ns duplex-link-op $n2 $n3 queuePos 0.5
#Create a UDP agent and attach it to node n0
set udp0 [new Agent/UDP]
$udp0 set class_ 1
$ns attach-agent $n0 $udp0
# Create a CBR traffic source and attach it to udp0
set cbr0 [new Application/Traffic/CBR]
$cbr0 set packetSize_ 500
$cbr0 set interval_ 0.005
```

\$cbr0 attach-agent \$udp0

#Create a UDP agent and attach it to node n1 set udp1 [new Agent/UDP] \$udp1 set class_ 2 \$ns attach-agent \$n1 \$udp1


Create a CBR traffic source and attach it to udp1 set cbr1 [new Application/Traffic/CBR] \$cbr1 set packetSize_ 500 \$cbr1 set interval_ 0.005 \$cbr1 attach-agent \$udp1

#Create a Null agent (a traffic sink) and attach it to node n3 set null0 [new Agent/Null] \$ns attach-agent \$n3 \$null0

#Connect the traffic sources with the traffic sink \$ns connect \$udp0 \$null0 \$ns connect \$udp1 \$null0

#Schedule events for the CBR agents \$ns at 0.5 "\$cbr0 start" \$ns at 1.0 "\$cbr1 start" \$ns at 4.0 "\$cbr1 stop" \$ns at 4.5 "\$cbr0 stop" #Call the finish procedure after 5 seconds of simulation time \$ns at 5.0 "finish"

#Run the simulation \$ns run



Practical: 8

