


Name: Andrew B. Coral
Program-Section: BSIT 2-2

Date: May 8, 2025
Course: Network Administration

Cisco Packet Tracer Activity: Configuring Dynamic Routing (RIP)

Steps

1. Open your saved Cisco Packet Tracer activity:




Configure RIP on R0

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#version 2
Router(config-router)#network 10.0.1.0
Router(config-router)#network 10.0.2.0
Router(config-router)#network 10.0.3.0
Router(config-router)#network 10.0.4.0
Router(config-router)#no auto-summary
Router(config-router)#exit
Router(config)#exit
Router#
%SYS-S-CONFIG_I: Configured from console by console
write memory
Building configuration...
[OK]
Router#
```

Copy Paste

Configure RIP on R1




The screenshot shows a window titled 'R1' with tabs for 'Physical', 'Config', 'CLI', and 'Attributes'. The 'CLI' tab is active, displaying the 'IOS Command Line Interface'. The interface shows the following commands and output:

```
Press RETURN to get started.

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#version 2
Router(config-router)#network 10.0.1.0
Router(config-router)#network 10.0.5.0
Router(config-router)#no auto-summary
Router(config-router)#
% Invalid input detected at '^' marker.
Router(config-router)#no auto-summary
Router(config-router)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
write memory
Building configuration...
[OK]
Router#
```

At the bottom of the CLI window, there are 'Copy' and 'Paste' buttons, and a 'Top' link.

Configure RIP on R2




The screenshot shows a window titled 'R2' with tabs for 'Physical', 'Config', 'CLI', and 'Attributes'. The 'CLI' tab is active, displaying the 'IOS Command Line Interface'. The interface shows the following commands and output:

```
Press RETURN to get started.


Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#version 2
Router(config-router)#network 10.0.2.0
Router(config-router)#network 10.0.5.0
Router(config-router)#network 10.0.6.0
Router(config-router)#no auto-summary
Router(config-router)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
write memory
Building configuration...
[OK]
Router#
```

At the bottom of the CLI window, there are 'Copy' and 'Paste' buttons, and a 'Top' link.

Configure RIP on R3



Configure RIP on R4



Verification:

