Public (PU)

Read-only look-ups and reports that every user can open: find a lot, list jobs, see plan material and start-pack labor.

1. What this module is for

Public is the shared "quick answers" area. Anyone in the company can find a lot by its address, see which job, phase, bid, plan and packs it belongs to, print job lists, look at the standard and option material of a plan, and print the labor of a start pack. Nothing here is entered or changed: it only reads data kept by other modules.

Public is open to every user. It does not need a permission flag and no login is blocked from it.

2. How it connects to other modules

Needs data from

MODULE	WHAT IT USES	WHY
Job setup	Customers, jobs, phases, lots, packs on lots, schedule stages of lots	Every lot and job look-up and list comes from here
Plan management	PM customers, jobs, bids (contracts), plans, packs and material	Plan data and start-pack labor are read from the plans
Inventory	Item descriptions and codes	Shows the material and labor item on plan and start-pack reports
Database maintenance (lists)	Status, division, schedule stage, superintendent, job type, pack type, stage, work type and phase type lists	Fill the drop-downs and the names on the reports

Feeds data to

None. Public only reads data and does not write anything to the database.

Where it sits in the work flow

Public is used at any point, usually before or while working in another module: to confirm a lot's address and plan, to check which jobs are active, or to print the labor a crew will be paid for a lot. The data comes from Plan management (plans and packs) and Job setup (jobs and lots), so a look-up is only as complete as those modules.

3. Screens (tabs) in this module

SCREEN / TAB	WHAT IT IS FOR	WHAT YOU CAN DO THERE
Lot finder (page title "Public look-ups")	Find a lot by address	Type part of an address or house number, click a match, see the "Address lot search" sheet, print it
Job lists	Four job lists	Residential job list, PM job list by customer, Jobs by city, Jobs by division & status
Lot reports	Two lot reports	Lot info search, Status search
Plan data	Plan material of a PM plan	Plan standard data, Plan option data
Start pack labor	Labor items of a start pack	Start pack labor - lot, Start pack labor - phase

4. How the data entry forms work

There are no data entry forms in this module. Every screen only has filters (drop-downs and a search box) that decide what a report shows. The filters work like this:

- Pick-lists depend on each other. In the lot reports you pick a Job first, and only then does the Lot list fill with that job's lots (closed lots show their close date). Phase works the same way after Job.
- For plan data you pick PM customer, then PM job, then PM bid, then PM plan; each list stays empty until the one before it is chosen, and changing an earlier choice clears the later ones.
- A report only appears once all of its filters are chosen. Until then the page says "Complete the filters above".

- Nothing is saved when you use these screens, so there is nothing to cancel or confirm.

5. Reports

REPORT	WHAT IT SHOWS	FILTERS YOU CHOOSE FIRST	PRINT / EXPORT
Address lot search (on Lot finder)	One lot: customer, job, phase, bid, superintendent, plan, permit, status, dates, warranty, invoice number, notes, and its packs	Type part of the address, then click the address	Print
Residential job list	Every job with customer, status and superintendent, grouped by division	None	Print, CSV
PM job list by customer	Plan management jobs (templates left out) by division and customer, with job type, spec level and status	None	Print, CSV
Jobs by city	Jobs of a division and status, grouped by city	Division, Status (can be "1-All status")	Print, CSV
Jobs by division & status	Jobs of a division and status, grouped by customer	Division, Status (can be "1-All status")	Print, CSV
Lot info search	Same lot sheet as the address search, chosen by job and lot	Job, Lot	Print, CSV
Status search	Lots of a division that have one status, grouped by customer, job and phase	Division, Status (one status, not "All")	Print, CSV
Plan standard data	Standard packs and their material for one PM plan	PM customer, PM job, PM bid, PM plan	Print, CSV
Plan option data	Option packs and their material for one PM plan	PM customer, PM job, PM bid, PM plan	Print, CSV
Start pack labor - lot	Labor items, quantities and prices of one lot at a schedule stage, with subtotal and total	Job, Lot, Schedule stage	Print, CSV
Start pack labor - phase	The same for every lot of a phase	Job, Phase, Schedule stage	Print, CSV


6. Action buttons

None. The only buttons are Print and CSV (save the report as a spreadsheet file) on the reports, which do not change any data.


7. A typical day-to-day workflow

1. Open Public and type part of an address on Lot finder.
2. Click the right address to see the lot sheet: job, plan, bid, superintendent and packs. Print it if needed.
3. Open Job lists and choose the Residential job list to see active and closed jobs by division, or Jobs by city for one division.
4. Open Lot reports. Use Lot info search when you know the job and lot, or Status search to list every lot of a division with a given status.
5. Open Plan data, choose the PM customer, job, bid and plan, and view the standard or option material.
6. Open Start pack labor, choose the job and lot (or phase) and the schedule stage, and print the labor to hand to a foreman.
7. Use CSV to open any list in Excel.

8. Screenshots



Lot finder: addresses matching "Granite" and the lot sheet of the chosen lot



Job lists: the Residential job list grouped by division

9. Good to know

- Public never changes data. To correct a lot, plan or job, use Job setup or Plan management.

- The job lists leave out customers whose name starts with "Test", and the city and division lists also leave out jobs with "Test" in the name.
- "1-All status" means every real job status. The Status search needs one specific status.
- The address search needs the lot's phase to have a superintendent and a bid; if it does not, the sheet says nothing is found and you can use Lot info search instead, which does not require them.
- Lot status in the address search is the lot's own status; in Lot info search it is the job's status. This follows the two Access reports.
- Start pack labor shows only labor items (cost code L), only active material, and only packs whose total quantity on the lot is not zero. Stages hidden from start-pack labor in Plan management do not appear.
- If a job has more than one superintendent on its phases, the job lists show one of them.