

## INSTALLATION AND SETUP HANDBOOK OF PAYU LATAM'S PLUGIN FOR VIRTUEMART


## 1. System Requirements

- Installation based on Joomla 2.5 with MySql 5.1 +
- Have Virtuemart versión 2+ installed

Download PayU's VIRTUEMART plugin which you can find in this section.

## 2. Installation

• In the Joomla Administrator console, access the Extension Manage's menu.



• Select the "Upload Package File" in the installation screen and find the payulatam.zip file.



• Afterwards the message confirming that the installation was successful has to be displayed.






## 3. Configuration

• Select the "Payment Methods" option in the VirtueMart configuration page and then the "New" option.




 In the "Payment Method Information" tab select "PayuLatam" as the Payment Method option.



 You should type the PayU Latam shop's account and password information in the settings tab, and the URL connection to the Gateway and other configuration variables.





(Test URL: https://sandobox.gateway.payulatam.com/ppp-web-gateway)

The configuration variables are described below:

Field	Value
Logo	Configuration of the logo that will show in your payment PayUlatam method
Test URL	The Gateway's testing URL, you can use the https://sandbox.gateway.payulatam.com/ppp-web-gateway URL
Production URL	For production you should use the https://gateway.payulatam.com/ppp-web-gateway/ URL
Test mode	If you want to make transactions in test mode,



	<del>,</del>
	select the yes radio button. If you have the test mode active, the test URL "Test URL" is used.
Merchant ID	The shop's ID in PayU Latam
Account ID	PayU account ID, according to the country in which you want to sell.
API Key	This is provided by PayU Latam and is unique for the shop; you can find it in PayU Latam's administrative module.
Section "ORDER STATUS PARAMS"	Defines the order's status in VirtueMart, according to the transaction status returned by PayuLatam. It is recommended to use the default plugin status; however you can configure them according to your business needs.
Currency	You must set the currency in USD. You can also configure the relevant currency of Account ID's country. Example COP if you sell in Colombia.
Minimum value – Maximum value	The total value of an order must be within this range in order to activate the PayUlatam payment means.
Cost per transaction	Not applicable because the commission rates vary depending on PayU's payment means.
Total percent per cost	Not applicable because the commission rates vary depending on PayU's payment means.
Tax	To use this option you must first configure the Virtuemart rule which corresponds to the tax that is associated with the transaction. For example VAT for Colombia

• Finally, select the "Save" or "Save and Close" option.

Now your customers can pay with PayU Latam using the VIRTUEMART shopping cart.