

EXPERIMENT NO:-04

AIM:- To study about the process of configuring Inter-connection of LANs by using Cisco Packet Tracer.

● STEPS :


1. After this we select Network Devices from that we find routers, switches, hub and etc. but we take a switch, some PCs and connect like this with wire.

• Connect PCs to Switches:


- Use the **copper straight-through cable** to connect:
 - PC0 to Switch0
 - PC1 to Switch0
 - PC2 to Switch1
 - PC3 to Switch1

• Connect Switches to the Router:

- Use the **copper straight-through cable** to connect:
 - Switch0 to the **FastEthernet 0/0** port on the router.
 - Switch1 to the **FastEthernet 0/1** port on the router.




2. After this click on the Router1 go a window will open go to Config and select GigabitEthernet0/0 and GigabitEthernet0/1 one by one and set IP address and click on the Port Status to On it.





3. Assign IP Addresses to PCs:

- Click on each PC and go to the **Desktop tab > IP Configuration**.
- Assign the following IPs:
 - **PC0:** 155.1.1.1, Subnet Mask: 255.255.255.0, Default Gateway: 155.1.1.0
 - **PC1:** 155.1.1.2, Subnet Mask: 255.255.255.0, Default Gateway: 155.1.1.0
 - **PC2:** 156.1.1.1, Subnet Mask: 255.255.255.0, Default Gateway: 156.1.1.0
 - **PC3:** 156.1.1.2, Subnet Mask: 255.255.255.0, Default Gateway: 156.1.1.0



4. Click on Add Simple PDU to send one PC1 to PC3 message. To do that select first msg box and click to PC1 and to send another PC click to that PC.




5. After that click on simulation which in the right bottom and play to visualization and there so all the event when what happening.


Event List		
Vis.	Time(sec)	Last Device
	0.000	--
	0.001	PC0
	0.002	Switch0
	0.003	Router1
	0.004	Switch1
	0.005	PC2
	0.006	Switch1
	0.007	Router1
	0.008	Switch0
	0.031	--
Visible	0.032	Switch0
Visible	0.032	Switch0

6. After Done this we find the all detail about the process below. Like in the image show that.

Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit	Delete
	Successful	PC0	PC2	ICMP		0.000	N	0	(edit)	(delete)



7. After this we go to again Desktop and now we select Command Prompt.



```
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 10.1.1.2

Pinging 10.1.1.2 with 32 bytes of data:

Reply from 10.1.1.2: bytes=32 time<1ms TTL=128
Reply from 10.1.1.2: bytes=32 time=6ms TTL=128
Reply from 10.1.1.2: bytes=32 time<1ms TTL=128
Reply from 10.1.1.2: bytes=32 time<1ms TTL=128

Ping statistics for 10.1.1.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 6ms, Average = 1ms
```