

RAM (cont.)




RAM (cont.)


- When you talk about the memory of a computer, most often you're talking about its RAM.
- If a program is stored in RAM, that means that a sequence of instructions are stored in consecutively addressed bytes in the RAM.
- Data values (variables) are stored anywhere in RAM, not necessarily sequentially
- Both instructions and data are accessed from RAM using addresses
- RAM is one (crucial) part of the computer's overall architecture

Computer Architecture







Computer Architecture




- What is a bus?
- It is a simplified way for many devices to communicate to each other.
- · Looks like a "highway" for information.
- Actually, more like a "basket" that they all share.






 Suppose CPU needs to check to see if the user typed anything.




 CPU puts "Keyboard, did the user type anything?" (represented in some way) on the Bus.




"Keyboard, did the user type anything?"

 Each device (except CPU) is a State Machine that constantly checks to see what's on the Bus.




"Keyboard, did the user type anything?"

 Keyboard notices that its name is on the Bus, and reads info. Other devices ignore the info.




"Keyboard, did the user type anything?"

Keyboard then writes "CPU: Yes, user typed 'a'."
 to the Bus.




"CPU: Yes, user typed 'a'."

 At some point, CPU reads the Bus, and gets the Keyboard's response.



"CPU: Yes, user typed 'a'."

Computer Architecture



Inside the CPU

- The CPU is the brain of the computer.
- It is the part that actually executes the instructions.

Let's take a look inside.

Memory Registers

Register 0

Register 1

Register 2

Register 3

Temporary Memory.
Computer "Loads" data
from RAM to registers,
performs operations on
data in registers, and
"stores" results from
registers back to RAM

Remember our initial example: "read value of A from memory; read value of B from memory; add values of A and B; put result in memory in variable C." The reads are done to registers, the addition is done in registers, and the result is written to memory from a register.

Memory Registers

Register 0

Register 1

Register 2

Register 3

Arithmetic
/ Logic
Unit

For doing basic
Arithmetic / Logic
Operations on Values stored
in the Registers

Memory Registers

Register 0

Register 1

Register 2

Register 3

Instruction Register

Arithmetic
/ Logic
Unit

To hold the current instruction

Memory Registers

Register 0

Register 1

Register 2

Register 3

Instruction Register

Instr. Pointer (IP)

Arithmetic
/ Logic
Unit

To hold the address of the current instruction in RAM

Memory Registers

Register 0

Register 1

Register 2

Register 3

Instruction Register

Instr. Pointer (IP)

Arithmetic
/ Logic
Unit

Control Unit (State Machine)

The Control Unit


- It all comes down to the Control Unit.
- · This is just a State Machine.

How does it work?

The Control Unit


- Control Unit State Machine has very simple structure:
 - 1) Fetch: Ask the RAM for the instruction whose address is stored in IP.
 - 2) Execute: There are only a small number
 of possible instructions.
 Depending on which it is, do
 what is necessary to execute it.
 - 3) Repeat: Add 1 to the address stored in IP, and go back to Step 1!


The Control Unit is a State Machine





A Simple Program


- Want to add values of variables a and b (assumed to be in memory), and put the result in variable c in memory, I.e. c ← a+b
- Instructions in program
 - Load a into register r1
 - Load b into register r3
 - $-r2 \leftarrow r1 + r3$
 - Store r2 in c














Computer has many parts, connected by a Bus:




- The RAM is the computer's main memory.
- This is where programs and data are stored.



 The CPU goes in a never-ending cycle, reading instructions from RAM and executing them.




 This cycle is orchestrated by the Control Unit in the CPU.




Back to the Control Unit

 It simply looks at where IP is pointing, reads the instruction there from RAM, and executes it.



 To execute an instruction, the Control Unit uses the ALU plus Memory and/or the Registers.



Programming

Where we are

- Examined the hardware for a computer
 - Truth tables
 - Logic gates
 - States and transitions in a state machine
 - The workings of a CPU and Memory

Now, want to program the hardware

Programs and Instructions

- Programs are made up of instructions
- CPU executes one instruction every clock cycle
 - Modern CPUS do more, but we ignore that
- Specifying a program and its instructions:
 - · Lowest level: Machine language
 - Intermediate level: Assembly language
 - Typically today: High-level programming language

Specifying a Program and its Instructions

High-level programs: each statement translates to many instructions Load a into r1
 E.g. c ← a + b to: Load b into r3

 $r2 \leftarrow r1 + r3$ Store r2 into c

- Assembly language: specify each machine instruction, using mnemonic form
 - E.g. Load r1, A
- Machine language: specify each machine instruction, using bit patterns
 - E.g. 1101101000001110011

Machine/Assembly Language

- We have a machine that can execute instructions
- Basic Questions:
 - What instructions?
 - How are these instructions represented to the computer hardware?

- Computers used to have very complicated instruction sets - this was known as:
 - CISC = Complex Instruction Set Computer
 - Almost all computers 20 years ago were CISC.

- 80s introduced RISC:
 - RISC = Reduced Instruction Set Computer

- RISC = Reduced Instruction Set Computer
 - Fewer, Less powerful basic instructions
 - But Simpler, Faster, Easier to design CPU's
 - Can make "powerful" instructions by combining several wimpy ones

 Shown to deliver better performance than Complex Instruction Set Computer (CISC) for several types of applications.

- Nevertheless, Pentium is actually CISC!
- · Why?

- Nevertheless, Pentium is actually CISC!
- Why: Compatibility with older software

 Newer application types (media processing etc) perform better with specialized instructions

 The world has become too complex to talk about RISC versus CISC

Typical Assembly Instructions

- Some common assembly instructions include:
 - 1) "Load" Load a value from RAM into one of the registers
 - 2) "Load Direct" Put a fixed value in one of the registers (as specified)
 - 3) "Store" Store the value in a specified register to the RAM
 - 4) "Add" Add the contents of two registers and put the result in a third register

Typical Assembly Instructions

- Some common instructions include:
 - 5) "Compare" If the value in a specified register is larger than the value in a second register, put a "0" in Register r0
 - 6) "Jump" If the value in Register r0 is "0", change Instruction Pointer to the value in a given register
 - 7) "Branch" If the value in a specified register is larger than that in another register, change IP to a specified value

Machine Languages

- Different types of CPU's understand different instructions
 - Pentium family / Celeron / Xeon / AMD K6 / Cyrix ... (Intel x86 family)
 - PowerPC (Mac)
 - DragonBall (Palm Pilot)
 - StrongARM/MIPS (WinCE)
 - Many Others (specialized or general-purpose)
- They represent instructions differently in their assembly/machine languages (even common ones)