



Blender keyboard shortcuts and viewport navigation

X Y Z

3D Navigation via Gizmo



Click or drag the gizmo

Axis label: jump to that orthographic view.

Matching empty circle: jump to the opposite view.

Hover near the gizmo to reveal a circle; drag inside it to orbit.



Use the four tool icons

Magnifying glass: drag up/down to zoom.


Hand: drag to pan up, down, left, or right.

Camera: toggle camera view.

Grid: toggle orthographic / perspective.

3D Navigation via Number Pad

NAVIGATING WITH THE KEYBOARD'S NUMBER PAD



Numberpad corner keys jump to fixed views or their opposite. The even numbers orbit the view in that cardinal direction.

+ zooms in.

- zooms out.

NAVIGATING WITH THE MIDDLE MOUSE BUTTON

Orbit Drag with the **middle mouse button** to rotate the camera around your scene.

Pan Hold **Shift** and drag with the middle mouse button to slide the view.

Tip: If you lose your object, select it in the Outliner, click back in the viewport for focus, and press **.** on the numberpad to bring it back into view.

Simple workflow

REPEAT THIS LOOP

1. Select your target (objects in **Layout**; vertex/edge/face when **Modeling**).
Use **Shift** to add to existing selection.
2. Select action/transform type (**G**rab/**R**otate/**S**cale)
3. **Optional:** Constrain **X**/**Y**/**Z** axis
4. Move mouse (no mouse button) for amount and direction (no mouse button), using **Shift** for precision or **Ctrl** for increments, or type a numeric value.
5. **Enter** to commit, or **ESC** to cancel & revert

Transform selected

MAKING CHANGES

When an object, face, edge, or vertex is selected, use these commands for basic changes.

G Grab / move
Press **G** to move. Add **X**, **Y**, or **Z** to stay on one axis.
G + **X** → move along X
Shift makes smaller movements.

R Rotate
Press **R** to rotate. Add **X**, **Y**, or **Z** to rotate around that axis.
R + **X** → rotate around X **R** + **R** → free rotate

S Scale
Press **S** to make the object larger or smaller. Add **X**, **Y**, or **Z** to stretch on one axis.
S + **X** → stretch along X

Finish or undo: **Enter** commits a move, rotation, or scale. **Esc** backs out and reverts it.

Undo or adjust

CORRECTING MISTAKES

Ctrl + **Z** **Undo** — reverse the last action.
Shift + **Ctrl** + **Z** **Redo** — restore the action.
F9 **Adjust last operation** — reopen the last operation's settings.

Remember: red = X, green = Y, blue = Z. The colored gizmo labels match these axes.

Modeling mode

TOP-ROW NUMBERS

In **Edit Mode**, the top-row number keys choose what part of a mesh you select:

1 Points / vertices
2 Edges
3 Faces

Easy to mix up: numberpad **1** is a front view; top-row **1** is vertex selection in Edit Mode.

Viewport controls

PANELS + TOOLS

N **Sidebar** on/off — the right-side panel for numerical tweaks to your most recent change.
T **Toolbar** on/off — the tool shelf on the left side of the viewport.
Shift + **A** **Add an object** — opens the Add menu.