Device	INTERFACE	DESCRIPTION	IP ADDRESS	SUBNETMASK	DEFAULT GATEWAY
Router-Hamilton-Edge	G0/0 G0/1	TO OUTSIDE TO MASTER	PUBLIC IP 10.1.1.1	N/A 255.255.255.0	N/A N/A
	G/2	ROTUER TO BACKUP	10.1.2.1	255.255.255.0	N/A
Router-Hamilton-Master	G0/0	ROUTER TO EDGE	10.1.1.2	255.255.255.0	N/A
		ROUTER TO MASTER			
	G0/1	SWITCH	172.16.0.1	255.255.255.0	N/A
	HSRP	VIRTUAL IP TO EDGE	172.16.0.19	255.255.255.0	N/A
	G0/0	ROUTER	10.1.2.2	255.255.255.0	N/A
Router-Hamilton-Backup	G0/1	TO MASTER SWITCH	172.16.0.2	255.255.255.0	N/A
	HSRP	VIRTUAL IP	172.16.0.19	255.255.255.0	N/A
	G0/0	TO MASTER ROTUER	N/A	N/A	N/A
	G0/1 G0/2	TO DISTRO 2	N/A	N/A	N/A
	G0/3	TO MASTER ASA	N/A	N/A	N/A
Hamilton-Distro-Master	G1/0 G1/1	TO DISTRO 3	N/A	N/A	N/A
	G1/2	TO LAN SWITCH	N/A	N/A	N/A
	G1/3	TO PROXY SWITCH	N/A	N/A	N/A
	G0/0	TO BACKUP ROTUER	N/A	N/A	N/A
	G0/1 G0/2	TO DISTRO MASTER	N/A	N/A	N/A
	G0/3	TO BACKUP ASA	N/A	N/A	N/A
Hamilton-Distro-2	G1/0 G1/1	TO DISTRO 3	N/A	N/A	N/A
	G1/2	TO LAN SWITCH	N/A	N/A	N/A
	G1/3	TO PROXY SWITCH	N/A	N/A	N/A
	G0/0 G0/1	TO DISTRO 2	N/A	N/A	N/A
Hamilton-Distro-3	G0/2 G0/3	TO DISTRO MASTER	N/A	N/A	N/A
	G1/0	TO LAN SWITCH	N/A	N/A	N/A
	G0/0	TO Proxy Server	N/A	N/A	N/A
Access-Hamilton-Proxy	G0/1	TO DISTRO MASTER	N/A	N/A	N/A
	G0/2	TO DISTRO 2	N/A	N/A	N/A
	G0/0	TO DISTRO MASTER	N/A	N/A	N/A
Access-Hamilton-LAN	G0/1	TO DISTRO 2	N/A	N/A	N/A
Access-Haiiillillil-LAN	G0/2	TO DISTRO 3	N/A	N/A	N/A
	~~~	PC PC	N/A N/A	N/A N/A	N/A N/A
Proxy-Server	G0/0	TO OUTSIDE	PUBLIC IP	N/A N/A	N/A N/A
	G0/1	TO PROXY SWITCH	172.16.0.5	255.255.255.0	N/A
ASA-Hamilton-Master	G0/0	TO DISTRO MASTER	172.16.0.3	255.255.255.0	N/A
	G0/1	FAILOVER	192.168.1.1	255.255.255.0	N/A
	G0/2	STATEFUL	192.168.2.1	255.255.255.0	N/A
	G0/3	TO SERVER MASTER	10.10.0.1	255.255.255.0	N/A
	G0/0	SWITCH TO DISTRO 2	N/A	N/A	N/A
ASA-Hamilton-Backup	G0/0	FAILOVER	192.168.1.2	255.255.255.0	N/A
-	G0/2	STATEFUL	192.168.2.2	255.255.255.0	N/A

	G0/3	TO SERVER BACKUP SWITCH	N/A	N/A	N/A
	G0/0	TO ASA	N/A	N/A	N/A
Hamilton-Server-Master	G0/1 GO/2	TO SERVER BACKUP SWITCH	N/A	N/A	N/A
	~~~	PC	N/A	N/A	N/A
Hamilton-Server-Backup	G0/0	TO ASA	N/A	N/A	N/A
	G0/1 GO/2	TO SERVER MASTER SWITCH	N/A	N/A	N/A
	~~~	PC	N/A	N/A	N/A
PCs	~~~	TO LAN SWITCH	172.16.0.20 - 255	255.255.255.0	172.16.0.19
HA-Hamilton-Master	~~~	TO SERVER SWITCH	10.10.0.99	255.255.255.0	10.10.0.1
HA-Hamilton-Backup	~~~	TO SERVER SWITCH	10.10.0.101	255.255.255.0	10.10.0.1
HA-Hamilton-Server	~~~	VIRTUAL IP	10.10.0.100	255.255.255.0	10.10.0.1
Hamilton-Admin	~~~	TO SERVER SWITCH	10.10.0.110	255.255.255.0	10.10.0.1

AUCKLAND						
Router-Auckland	G0/0	TO OUTSIDE	PUBLIC IP	N/A	N/A	
	G0/1	TO SWITCH	172.17.0.1	255.255.255.0	N/A	
Switch-Auckland	G0/0	TO ROUTER	N/A	N/A	N/A	
PCs	~~~	TO SWITCH	172.17.0.20 ~ 255	N/A	172.17.0.1	

ROTORUA						
Router-Rotorua	G0/0	TO OUTSIDE	PUBLIC IP	N/A	N/A	
	G0/1	TO SWITCH	172.18.0.1	255.255.255.0	N/A	
Switch-Rotorua	G0/0	TO ROUTER	N/A	N/A	N/A	
PCs	~~~	TO SWITCH	172.18.0.20 ~ 255	N/A	172.18.0.1	

THAMES						
Router-Thames	G0/0	TO OUTSIDE	PUBLIC IP	N/A	N/A	
	G0/1	TO SWITCH	172.19.0.1	255.255.255.0	N/A	
Switch-Thames	G0/0	TO ROUTER	N/A	N/A	N/A	
PCs	~~~	TO SWITCH	172.19.0.20 ~ 255	N/A	172.19.0.1	