

Slide 1 of 11

Literate

Exampl

Next Step

Literate Software Development

Dan Szymczak

Computing and Software Department Faculty of Engineering McMaster University

Ernie Mileta Visit, Dec. 11, 2014



Slide 2 of 11

Softwar

. .

Next Step

Overview

1 Literate Software Development.

2 Example.

3 Next Steps.



Slide 3 of 11

Literate Software

Examp

Next Steps

Literate Software Development for Scientific Software

Motivation

- Improve the qualities of verifiability, maintainability and reusability.
- Save money and time when managing change.
- One "source," multiple views
 - · Requirements, including or excluding derivations.
 - Design
 - Test Cases
 - Build instructions
 - ...

Advantages

- Reuse chunks and transformed chunks to avoid duplication.
- Improve understandability, traceability and reproducibility.
- Increased flexibility



Slide 4 of 11

Literate Softwar

Example

Next Step

Example: h_g and h_c A simple example taken from the SRS for FP

 h_g and h_c are symbols which appear in several locations including:

- The Software Requirements Specification
- The Literate Programmer's Manual
- The Source Code

Let's take a look!



Slide 5 of 11

Literate Softwar

Example

Next Step

Example: h_g and h_c SRS Definition for h_g

| Number | DD1 |
|-------------|--|
| Label | h_g |
| Units | $ML^{0}t^{-3}T^{-1}$ |
| SI | $\frac{W}{m^2(^{\circ}C)}$ |
| Equation | $h_{\mathcal{G}} = \frac{2k_{\mathcal{C}}h_{\mathcal{P}}}{2k_{\mathcal{C}} + \tau_{\mathcal{C}}h_{\mathcal{P}}}$ |
| Description | h_g is the gap conductance $	au_c$ is the clad thickness h_p is initial gap film conductance k_c is the clad conductivity NOTE: Equation taken from the code |
| Sources | source code |



Slide 6 of 11

Softwar

Example

Next Step

Example: h_g and h_c LPM Definition for h_g

$$h_g = \frac{2k_c h_p}{2k_c + \tau_c h_p} \tag{1}$$

The corresponding C code is given by:



Slide 7 of 11

Literate Softwar

Example

Next Step

Example: h_g and h_c A simple example taken from the SRS for FP

Modifying h_g or h_c to reflect changes in requirements is not a simple matter. It involves the following steps (at the very least):

- Update the definition in the SRS, LPM, and all other documents which reference the symbol
- Modify the source code to reflect the new requirements
- Trace all dependencies
- Modify dependents to accommodate the change
- Ensure each of the documents is now up to date and consistent



Slide 8 of 11

Literate

Example

Next Step

Example: h_g and h_c Simplifying the process

What if we could maintain everything in one source?



Slide 9 of 11

Software

Example

Next Step

Example: h_g and h_c

@Type Data Definition @Number 1

@Symbol h_g

@Description
h_g is the gap conductance
!{tau_c}.Description
!{h_p}.Description
!{k_c}.Description

@Equation

. . .



Slide 10 of 11

Literate

Next Steps

What next?

- Generate a document from our chunks
- Add options for different document "views"
 - · Ex. SRS with or without derivations
- Add options for additional document types
- Generate the source code from the equations!



Slide 11 of 11

Literate

Exampl

Next Steps

Thank You!