Binary Protocol

Command send by client

- Login
 - o 000 : login

[magic_number] 000 [packet_size] [username]

- Contact handling
 - o 001 : add contact

[magic_number] 001 [packet_size] [username]

o 002 : accept contact

[magic_number] 002 [packet_size] [username]

o 003 : reject contact

[magic_number] 003 [packet_size] [username]

o 004 : remove contact

[magic_number] 004 [packet_size] [username]

o 005 : get contact list

[magic_number] 005 [packet_size] [username]

- Call handling
 - 100: init call

[magic_number] 100 [packet_size] [username_1];[username_2];...

○ 101: accept call

[magic_number] 101

o 102 : reject call

[magic_number] 102 [packet_size] [call_id]

103: hang up

[magic_number] 103

Response send by server

- Connection
 - o 200 : connection accepted

[magic_number] 200

- Login
 - o 201 : logged in

[magic_number] 201 [packet_size] [username]

- Contact handling
 - o 203 : contact request accepted

[magic_number] 203 [packet_size] [username]

204 : contact request dismissed

[magic_number] 204 [packet_size] [username]

○ 205 : contact request transmitted

[magic_number] 205 [packet_size] [username]

o 206 : contact list

[magic_number] 206 [packet_size] [username_1];[username_2];...

o 207 : new contact request

[magic_number] 207 [packet_size] [username]

- Call handling
 - o 208 : call taken into account

[magic_number] 208

o 209: call accepted

[magic_number] 209 [packet_size] [caller_username:caller_ip];[username_1:ip_1];...

○ 210 : someone joined the call

[magic_number] 210 [packet_size] [username:ip]

o 211 : call request

[magic_number] 210 [packet_size] [caller_username:caller_ip]

• Error handling

○ 400 : bad request

[magic_number] 400 [packet_size] [message]

o 401 : already logged

[magic_number] 401 [packet_size] [username]

o 403 : not authorized

[magic_number] 403 [packet_size] [message]

o 404 : command not found

[magic_number] 404 [packet_size] [message]

○ 500 : internal server error

[magic_number] 500 [packet_size] [message]