

COS10004 Computer Systems


Lecture 4.5: Interrupts and Polling

CRICOS provider 00111D

Dr Chris McCarthy

CPU MULTI-TASKING - INTERRUPTS

A response to a signal that needs attention from the software



src: https://doc.micrium.com/display/os305/Handling+CPU+Interrupts





INTERRUPTS

Stacks allow interrupt-based hardware access.

- A device (e.g. I/O) issues an electrical signal, which feeds into a priority encoder which then issues an INT signal to the CPU (depending on relative priority).
- > The current work of the CPU (including the value of the IP) is **push**ed onto the stack.
- > The CPU loads the Interrupt's handler routine (code which specifies what to do when interrupted by the specific hardware), executes the code.
- The INT Handler ends with a RETurn instruction, which pops the stored IP off the stack into the IP, and processing resumes.



How I/O INTs work

- > Each hardware event is mapped to an Interrupt number, highest priority first (lowest).
- > Define an Interrupt vector table
 - an array of addresses of (pointers to) functions (int handlers) which execute depending on the interrupt level.
- Set up an Interrupt Mask enables or disables each interrupt type.
 - e.g. mask INT 0 (CTRL+ALT+DEL) if currently processing an INT 0.
- When an event is detected, control jumps to the table, to the INT handler code.



INTERRUPTS - USE HARDWARE SIGNALS TO RUN CODE


- > We need some logic to process these.
- Important interrupts (mouse move, keyboard, power down, Ctrl+Alt+Del, Ctrl+C) need a high priority.
- Unimportant (not-time-critical) things (function calls, GUI update) should have a lower priority.
- > We can use an encoder to read the electrical signals from hardware devices (ranked by priority), and to generate a binary INT number used to select the correct interrupt handler code.
 - the INT number will be used as the index of the INT vector table (an array of pointers).





> Here's one that processes 4 inputs (from 4 devices) and reports the INT number in 2-bit binary.

Four to Two Encoder







CAN'T INT AN INT

- Any routine can be interrupted, including the code loaded by an INT handler routine if the priority is higher.
- loading an INT handler is atomic
 - it can't be interrupted.
 - Uses MUTEXes (XOR gates) to implement INT masks.
- prevents an interrupt from being interrupted (which would cause the computer to become unresponsive, crash or entering an unstable state).
- An INT signal which occurs while another INT is being processed times-out and is repeated.





COMMON TYPES OF INTS

- > Clock actually a count-down timer which issues an INT each time it gets to 0.
- > Keyboard/Mouse
- > Error e.g. divide by zero error detected by the ALU.
- > Network a packet being received by the NIC (network interface controller).
- Exception generated by a try/catch instruction in software.
- > SysCall INT 80 (in assembly) triggers a kernel or system command to be executed.
- Hardware e.g. the power button generates an ATX event, CDROM ready.
- GUI events click, drag, button up, onfocus, onload...



POLLING

Polling is an alternative approach to interrupt


Check state/input of each hardware device in defined sequence:

process any change/input as needed.



- Can waste time checking hardware which is doing nothin
- Doesn't take advantage of the stack.
- If one device freezes, this can make the entire computer unresponsive.

> BUT! Relatively simple to implement





Examples: CDROM INT handlers as the CD is first read (*busy wait*). Also USB device checking



SUMMARY

Interrupts:

- Different processes/devices need CPU attention.
- Interrupts manage how CPU's handle these signals.
- Stacks provide basis for storing and recalling state while an INT is handled

> Polling:

- An alternative based on explicitly checking the state of devices/processes
- Simple to implement but generally considered wasteful of CPU cycles.



IN THE LAB...

> Play with Stacks ©



