

# **AnyMMO**

# AnyMMO Introduction

AnyRPG supports online play when [FishNet ↗](#) is installed.

To properly configure a game for online play, there are specific wizards, template content, prefabs, and Monobaviours that must be used. This section describes their use.

For full documentation of all the features that apply in both online and offline mode, see the [AnyRPG documentation ↗](#).

## Getting Started

### Guides: Jump right in

Follow our handy guides to get started on the basics as quickly as possible:

Installing AnyMMO



Creating your first game



Configuring your game



Installing Template Content





# GETTING STARTED

# Installing AnyMMO

AnyMMO is an addon for AnyRPG that enables online play.

Installing AnyMMO consists of 2 steps

## Install AnyRPG

Installing AnyRPG



## Install the AnyMMO Addon

AnyMMO (FishNet)





# Included sample games

AnyMMO includes a sample game. Read on to find out how to play it.

## Welcome Window

You can find links to the included sample games in the welcome window. The window will pop up automatically when you open the Unity project, but if you have just installed the package and not closed the Unity editor yet, you can still open it manually by clicking on the *Tools* menu in the menu bar and choosing *AnyRPG > Welcome Window*.






## AnyMMO FishNet Demo Game


The AnyMMO FishNet Demo Game is intended to be a simple demonstration of all features supported by AnyMMO. Since the majority of the content in the features demo game was installed using the Template Content Wizard, it also somewhat serves as an example of what type of template content can be quickly installed in your own games using the wizard.

## Loading the Game

To load the AnyMMO FishNet Demo game from the Welcome Window, click on the button with the game title.



This will open the loading scene for that game, at which point you can press the play button in the Unity editor to play the game.





# Creating your first game

Open the [New Game Wizard](#) to get started.

New Game Wizard



# Configuring your game

## The System Configuration Manager

All configuration options that apply to the entire game are set through the System Configuration Manager. For a full description of the common options that apply in both online and offline play, see the [base AnyRPG documentation](#).

This page will describe the options that apply exclusively in network mode. They can be found in the SystemConfigurationManager under the Network section.

## Network

| Name                         | Description                                                                                                                                                                                              |
|------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Server Backend               | The backend that will be used to store and retrieve player and account data. The File mode will store data in files on the local server and is appropriate for quick testing of single server instances. |
| API Server Address           | The address of the API server that the dedicated game server will connect to for database operations. Do not use a trailing slash.                                                                       |
| Validate API Server Cert     | This should only be set to false during development and testing when the APIServer is using a self-signed SSL certificate.                                                                               |
| API Server Shared Secret     | This is the shared secret that allows the game server to login to the API server.                                                                                                                        |
| Game Server Address          | This is the address (and optionally port) of the dedicated authoritative game server that all clients connect to. Users can change this value on the login window.                                       |
| Client Version               | If the server and client both do not have this version, the client will be told to upgrade.                                                                                                              |
| Client Download Url          | This is the address of a web page where the latest client can be downloaded.                                                                                                                             |
| Lobby Game Scene Names       | The list of scenes that can be chosen in lobby game mode.                                                                                                                                                |
| Private Message Chat Command | The chat command that is configured to send a private message (eg: tell or whisper)                                                                                                                      |
| Personal Instance Timeout    | The length of time (in minutes) a personal instance must be empty before the scene is unloaded. -1 means it never unloads.                                                                               |
| Group Instance Timeout       | The length of time (in minutes) a group instance must be empty before the scene is unloaded. -1 means it never unloads.                                                                                  |
|                              | The length of time (in minutes) a lobby game instance must be empty before the                                                                                                                           |

Lobby Game Instance Timeout

~ scene is unloaded. -1 means it never unloads.


World Instance Timeout

The length of time (in minutes) a world instance must be empty before the scene is unloaded. -1 means it never unloads.

# Installing Template Content

## Available Content


AnyMMO includes over 100 template content packages, that are all prefixed with the name FishNet.



## Handling Conflicts

When installing template content, if there are 2 packages with the same name, but one is prefixed with FishNet, the FishNet version of the content should be installed, to ensure the content works in online play mode.

For example, in the screenshot below, there are 2 Bread Template Packages. The one prefixed with FishNet should be installed, as the break pickup prefab, a type of *Interactable*, included in this package already has the *FishNetInteractable* component, and will work properly in online play.



# Running Your Game

Online games can be run in multiple ways. Read on to find out more.

## Client Build

To run an AnyMMO client, just ensure that when you create a build profile, you choose one of the non server build types.





## Server Build

There are three ways to run an AnyMMO server.

1. Running a server through the GUI with a normal build.
2. Running a server through the command line with a normal build.
3. Running a server with a server build.

## Server Options


The following options are available at run time and can be configured through the command line or GUI.

| Name        | Description                                                                                                                                                                                                                       | Command Line Switch                                                                                 | Example                                                                                                                            | Default Value |
|-------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------|---------------|
| Server Mode | <p><b>Lobby</b><br/>Players can host their own matches and other players can join. This mode is meant for Arena PVP/PVE type of play.</p> <p><b>MMO</b><br/>Players create characters and login to a persistent online world.</p> | <br>--servermode   | <br>--servermode<br>Lobby<br>--servermode<br>MMO | MMO           |
| Port        | The network port the server will listen on and clients will connect to.                                                                                                                                                           | <br>--serverport | <br>--serverport<br>1234                       | 7770          |


## Run A Server Through the GUI With A Normal Build

When making a normal (non server) build, you can choose to run the client or server using the same executable. To run the server, choose Play Online from the main menu and then click Host Server.





Choose the server mode and port and click Start Server



## Run A Server Through The Command Line With A Normal Build

To run a normal (non server) build in server mode through the command line, open a command prompt (terminal) and find the folder with the game executable, then run it with the following flags `-batchmode -nographics` .

```
Command Prompt
H:\unity\AnyRPG\builds\anyrpg-engine-1.0\build\anymmo-demo-game-1.0-0-windows>dir
Volume in drive H is LargeStorage
Volume Serial Number is 02DB-1A8D


Directory of H:\unity\AnyRPG\builds\anyrpg-engine-1.0\build\anymmo-demo-game-1.0-0-windows

04/19/2026  09:17 PM  <DIR>          .
04/19/2026  09:17 PM  <DIR>          ..
04/03/2026  11:52 AM             667,648 AnyRPG Engine.exe
04/19/2026  09:17 PM  <DIR>          AnyRPG Engine_BurstDebugInformation_DoNotShip
04/19/2026  12:01 PM  <DIR>          AnyRPG Engine_Data
04/03/2026  11:52 AM  <DIR>          D3D12
04/19/2026  09:17 PM             0 FishNet.SDK.Id
06/08/2025  12:00 AM  <DIR>          MonoBleedingEdge
04/03/2026  11:52 AM             1,609,648 UnityCrashHandler64.exe
04/03/2026  11:52 AM             35,810,224 UnityPlayer.dll
                                4 File(s)      38,087,520 bytes
                                6 Dir(s)      836,679,561,216 bytes free


H:\unity\AnyRPG\builds\anyrpg-engine-1.0\build\anymmo-demo-game-1.0-0-windows>".\AnyRPG Engine.exe" -batchmode -nographics
```

## Run A Server With A Server Build


Ensure that the type of server build you want is installed.




Click **Add Build Profile**.




Name your game build and click **Add Build Profile**.




Click **Add Settings** and then **Scene List**



Add all the scenes to the scene list that are in the non server build and ensure the profile is active.



With the profile active, click **Build**, or **Build And Run**.



To run the server, just run the executable. Since this is a server build, no extra command line switches are needed.

```
Command Prompt

H:\unity\AnyRPG\builds\anyrpg-engine-1.0\build\anymmo-demo-game-1.0-0-windows>dir
Volume in drive H is LargeStorage
Volume Serial Number is 02DB-1A8D

Directory of H:\unity\AnyRPG\builds\anyrpg-engine-1.0\build\anymmo-demo-game-1.0-0-windows

04/19/2026  09:17 PM    <DIR>          .
04/19/2026  09:17 PM    <DIR>          ..
04/03/2026  11:52 AM             667,648 AnyRPG Engine.exe
04/19/2026  09:17 PM    <DIR>          AnyRPG Engine_BurstDebugInformation_DoNotShip
04/19/2026  12:01 PM    <DIR>          AnyRPG Engine_Data
04/03/2026  11:52 AM    <DIR>          D3D12
04/19/2026  09:17 PM             0 FishNet.SDK.Id
06/08/2025  12:00 AM    <DIR>          MonoBleedingEdge
04/03/2026  11:52 AM             1,609,648 UnityCrashHandler64.exe
04/03/2026  11:52 AM             35,810,224 UnityPlayer.dll
               4 File(s)              38,087,520 bytes
               6 Dir(s)  836,679,561,216 bytes free

H:\unity\AnyRPG\builds\anyrpg-engine-1.0\build\anymmo-demo-game-1.0-0-windows>"AnyRPG Engine.exe"
```



# WIZARDS



# Wizards Introduction

AnyMMO creates new versions of a few existing wizards. When using the wizard system, if there is an AnyMMO specific version of a wizard, you should use it. This will ensure the game is setup correctly to function in online play mode.

In cases where there is not an AnyMMO specific version of a wizard, you can use the regular version of the wizard safely, as the content it creates does not depend on the network, and will work in both online and offline play modes.

New Game Wizard



New Scene Wizard



New Character Wizard



# New Game Wizard

The New Game Wizard will add a new game to your project and fully configure all the minimally required directories, scriptable objects, prefabs and scenes so it is ready to play immediately.


## New Game Wizard Documentation


This page only describes the additional options the AnyMMO New Game Wizard adds. For full documentation, see the [base New Game Wizard documentation](#).

.

## Accessing The Wizard

AnyMMO has its own New Game Wizard can be opened by clicking *Tools* in the menu bar, and selecting *AnyRPG > Wizard > FishNet > New Game Wizard*.





## Content Created

### Game Manager Prefabs

In the Prefab/GameManager folder you can find an additional prefab that is not created by the basic New Game Wizard.



### FishNetNetworkManager

The FishNetNetworkManager prefab contains all of the scripts necessary to configure and run the FishNet client and Fishnet server.

The FishNetNetworkManager should only ever exist in the game loading scene, which the wizard will have setup already.

# New Scene Wizard

The New Scene Wizard will add a new scene to your project based on an existing scene, or using a blank template scene.


## New Scene Wizard Documentation

This page only describes the additional options the AnyMMO New Scene Wizard adds. For full documentation, see the [base New Scene Wizard documentation](#) ↗.

## Accessing The Wizard

The New Scene Wizard requires that one of your game scenes with either a GameManager or SceneConfig object is open in the editor so that it can determine which game to install the content into.

The New Scene Wizard can be opened by clicking *Tools* in the menu bar, and selecting *AnyRPG > Wizard > FishNet > New Scene Wizard*.



# New Character Wizard

The new character wizard helps you import character models and set them up as NPC or player characters.


## New Character Wizard Documentation

This page only describes the additional options the AnyMMO New Character Wizard adds. For full documentation, see the [base New Character Wizard documentation](#) ↗.

## Accessing the Wizard

The new character wizard requires that one of your game scenes with either a GameManager or SceneConfig object is open in the editor so that it can determine which game to install the content into.

The New Character Wizard can be opened by clicking *Tools* in the menu bar, and selecting *AnyRPG > Wizard > FishNet > New Character Wizard*.



New Character Wizard

Creates a new character unit profile

 The attachment profile is not set. If this character is a humanoid, it will not be able to equip weapon models.

Script
FishNetNewCharacterWizard

Game
Game Name
New Game

Options
Create Unit Spawn Node
☐
Set As Default Player Char
☐

Prefab
Character Model
None (Game Object)

Unit Frame
Head Bone

Weapon Attachments
Attachment Profile
Add Weapon Attachments
☐
Left Hand Bone
Right Hand Bone
Left Arm Bone
Hip Bone
Spine Bone

Details
Character Name
Portrait Image
None (Sprite)

Animation Auto Assign
Assign Priority
Out Of Combat
Assign Clips
0

Animation Properties
Add Hit Events
☒
Animations

Network Settings
Is Mount
☐

 Character Model is required

Create

## Settings

This section describes the only the additional settings provided by AnyMMO New Character Wizard. See the [base documentation](#) for a full description of all common settings.

| Name     | Description                                                                                                                                                                      |
|----------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Is Mount | Due to the order objects are initialized over the network, mounts must have different base character object. Checking this option will ensure the UnitProfile is setup properly. |





# NETWORK BEHAVIOURS

# NetworkBehaviours Introduction

NetworkBehaviour is the base class provided by FishNet that is like a MonoBehaviour, but allows you to make API calls and synchronize state over the network.

AnyMMO adds several NetworkBehaviours to the game. By placing these components on the correct prefabs, the objects will function as expected when used in an online game.

Some Wizards, like the New Character Wizard, will do this for you. If you use the Template Content Wizard to install content with the prefix *FishNet*, any prefabs installed will already have the correct NetworkBehaviours on them.

Read on to discover which NetworkBehaviours are available, and which prefabs they must be placed on.

# FishNetCharacterModel

The FishNetCharacterModel NetworkBehaviour must be placed on the same character model prefab that contains the Unity *Animator* component.

It is automatically added to any model created by the AnyMMO New Character Wizard.

This component is responsible for ensuring character models are properly initialized when used in networked games.

# FishNetInteractable

The FishNetInteractable NetworkBehaviour must be placed on the same gameObject or prefab that contains the AnyRPG *Interactable* component.

The Interactables that are installed by any content prefixed with *FishNet* from the Template Content Wizard already have this component.

This component is responsible for synchronizing interactions with Interactables over the network.

# FishNetUnitController

The FishNetUnitController NetworkBehaviour must be placed on the same gameObject or prefab that contains the AnyRPG *UnitController* component.

The characters that are installed by any content prefixed with *FishNet* from the Template Content Wizard already have this component. Any characters created by the AnyMMO New Character Wizard will also already have this component.

This component is responsible for synchronizing character state over the network.

# FishNetObjectAudioController

The FishNetObjectAudioController NetworkBehaviour must be placed on the same gameObject or prefab that contains the AnyRPG *ObjectAudioController* component.

This component ensures that any object that should play sounds (like squeaky doors etc) will properly play the sound on the client.

# FishNetActivatableObject

The FishNetActivatableObject NetworkBehaviour must be placed on the gameObject that is used as the model for GatheringNodes and ItemPickups.

This component ensures that when the node is harvested or the item picked up, that the gameObject is properly set inactive on network clients.





# PREFABS

# Prefabs Introduction

AnyMMO includes several prefabs that should be included in certain scenes for the game to work properly in network mode.

FishNetNetworkManager



FishNetPhysicsSceneSync



# FishNetNetworkManager

The FishNetNetworkManager (or a variant of it) should be placed in the game loading scene, and linked to from both the *NetworkManagerClient* and *NetworkManagerServer* components of the GameManager prefab/variant in that scene.

Games created with the New Game Wizard have a variant of this prefab automatically placed in the loading scene.

This prefab contains all the scripts necessary to run the game in FishNet client or server mode.

# FishNetPhysicsSceneSync

The FishNetPhysicsSceneSync should be placed in any playable scene where characters will be active and physics is required. It should not be placed in the main menu or loading scenes.

Scenes created with the New Scene Wizard have this prefab automatically placed in them.

This prefab ensures that physics is properly simulated in any scene that is stacked. Scene stacking is the process of loading multiple scenes or copies of the same scene simultaneously on the server, such as instanced dungeons, and separating the physics so object in one scene do not collide with objects in another scene.

All scenes loaded on the server in online play mode are loaded as stacked scenes.