

Forecast Wall C7 Operations Console – How To Guide

System Overview

Forecast Wall C7 uses a single master engine plus small wall data files. Instead of maintaining many HTML pages, the engine loads wall content dynamically.

Example URL:
opswall.html?wall=radar

This loads:
walls/radar.js

Benefits:

- fewer files to edit
- consistent layout
- faster updates
- improved performance

Folder Structure

Place the forecastwall folder inside your GitHub Pages repository.

```
your-site/  
  index.html  
  trop.html  
  space.html  
  
  forecastwall/  
    opswall.html  
    wallconfig.js  
    walls/  
      wall-a.js  
      radar.js  
      satellite.js  
      tropical.js  
      surface.js  
      wind.js
```

Master Engine

opswall.html is the system engine.

Responsibilities:

- builds navigation
- loads wall data files
- renders maps
- handles zoom and dark mode
- refreshes images automatically

Navigation Configuration

Navigation is controlled in wallconfig.js.

Example:

```
const WALLS = [
  {id:"wall-a",name:"Wall-A"},
  {id:"radar",name:"Radar"},
  {id:"satellite",name:"Satellite"},
  {id:"tropical",name:"Tropical"},
  {id:"surface",name:"Surface"},
  {id:"wind",name:"Wind"}
];
```

Add a wall once here and the navigation updates automatically.

Wall Data Files

Each wall has a small configuration file.

Example: walls/radar.js

```
buildWall(
  "Radar Wall",
  [
    ["CONUS Radar","URL","Regional Radar","URL"],
    ["MRMS Reflectivity","URL","Composite Radar","URL"]
  ]
);
```

Format:

```
["Title","ImageURL","Title","ImageURL"]
```

Adding a Map

Open the wall file and add a new row:

```
["New Map Title","IMAGE_URL","New Map Title","IMAGE_URL"]
```

Adding a New Wall

1. Create a new file in the walls folder.

walls/newwall.js

2. Add the wall to wallconfig.js:

```
{id:"newwall",name:"New Wall"}
```

Linking From Your Website

Example link:

```
<a href="forecastwall/opswall.html?wall=wall-a">
Forecast Wall
</a>
```

Map Refresh

Images automatically refresh every 5 minutes.
The system adds a timestamp parameter to avoid browser caching.

Zoom Feature

Click any map to open a full-screen zoom view.
Click outside the image to close it.

Dark Mode

Dark mode reduces eye strain during long forecast sessions.
It can be toggled without reloading the page.

Deployment to GitHub Pages

1. Upload the forecastwall folder to your repository.
2. Commit changes.
3. Access:

`https://YOURUSERNAME.github.io/forecastwall/opswall.html`

Editing Workflow

Typical update process:

1. Open a wall file
2. Edit map URLs
3. Save and commit

Time required: usually under 30 seconds.

Conclusion

Forecast Wall C7 provides a scalable operational weather dashboard using static files compatible with GitHub Pages.
It simplifies maintaining large numbers of meteorological maps while keeping a professional forecast-wall interface.